Pierre-Luc Delisle Guillaume Nadeau Pour Tahar Mokhtari Dans le cours *Implanter un réseau* 12 Mai 2014

Rapport - Projet 2 Implanter un réseau



"Server consolidation is the most obvious, longstanding use case, but virtualization is like a Swiss army knife. You can use it in a number of different situations."









-Raghu Raghuram, Executive Vice President of Cloud Infrastructure and Management at VMware

Présentation du projet	5
Modifications apportées au projet	5
Tâches réalisées	8
Création d'un serveur de déploiement Microsoft	8
Partie 1 : Windows Server Update Services	9
WSUS via le registre Windows	44
Partie 2 : Windows Deployment Service	45
Partie 3 : Capture d'un poste existant	68
Création d'un serveur DFS (Distributed File System)	86
Partie 1 : Création des serveurs Samba	87
Partie 2 : Configuration du serveur DFS	93
Création d'un serveur LAMP	116
Partie 1 : Installation de MySQL	118
Partie 2 : Activation du pare-feu	121
Partie 3 : Installation de Apache HTTP Server	126
Partie 4 : Installation d'un module PHP	127
Partie 5 : Installation de PHPMyAdmin	129
Création d'un serveur Samba	134
Partie 1 : Désactivation de SELinux	135
Partie 2 : Installation du serveur Samba	136
Partie 3 : Activation du pare-feu	138
Partie 4 : Création d'un partage de fichiers	148
Création d'un serveur FTP	153
Partie 1 : Activation du pare-feu	154

Partie 2 : Installation du service	159
Partie 3 : Configuration du service	159
Partie 4 : test de la configuration	161
Création d'un serveur NAS	163
Partie 1 : Installation de NAS4Free	164
Partie 2 : Configuration de NAS4Free	171
Partie 3 : Configuration des disques	185
Partie 4 : Configuration d'un partage Windows sur NAS4Free	197
Partie 5 : Configuration d'un compte utilisateur	207
Installation d'une caméra IP	212
Partage d'une connexion Internet	213
Conclusion	215
Annexes	217
Annexe 1 : smb.conf	217
Annexe 2 : httpd.conf	229
Annexe 3 : vsftpd.conf	265
Notes	270

Présentation du projet

Dans le cadre du cours de fin d'études collégiales intitulé Implanter un réseau, nous avions pour deuxième projet la configuration de divers serveurs afin d'offrir des services sur le réseau.

Comme premier service réseau, nous avons déployé un serveur de déploiement. Ce serveur joue à la fois le rôle de déploiement de systèmes Microsoft Windows et le rôle de serveur de mises à jour Windows Update. De ce fait, ce même serveur pourra déployer autant des images Windows que des mises à jour du système d'exploitation. Ce service fut monté sur un serveur Microsoft Windows Server 2012 R2 Update 1.

Le deuxième service réseau était un service DFS, ou *Distributed File System*. Ce serveur rassemble en une interface tous les partages réseau d'un réseau. Ce service fut également mis en place sur un serveur Windows Server 2012 R2 Update 1.

Nous avions par la suite à mettre en place un serveur Linux. Ce serveur Linux disposait de trois services que nous avons jumelés, soit un service de partage de fichiers Samba, un service FTP et un service web Apache HTTP.

Un partage de connexion Internet ainsi que la configuration d'une caméra IP étaient également demandés.

Optionnellement, un serveur NAS, ou Network Attached Storage devait être mis en place sur le réseau. Nous avons choisi d'implanter le système Nas4Free.

Modifications apportées au projet

Ce projet n'avait pas de réelles directives quant à la manière de réaliser les tâches. Nous avons donc continué sur notre lancée et sur le réseau mis en place lors du premier projet, c'est-àdire en virtualisant tous les systèmes d'exploitation sur un hyperviseur VMware ESXi. Voici donc la topologie du réseau final que nous avons mis en place.



Comme vous pouvez le constater, nous avons beaucoup de serveurs pour assurer tous les services. Si nous en avons autant, c'est que nous avons suivi le modèle one service per VM, ou un service par machine virtuelle. De ce fait, nous exploitons directement le plus grand bénéfice de la virtualisation, soit le temps de disponibilité (uptime) accru. C'est le modèle de réseau qui est désormais le plus utilisé en entreprise lorsque la virtualisation est implantée. Ce modèle de réseau basé sur la ségrégation des services par machine virtuelle permet de décentraliser les services. Si un problème survient avec un service en particulier, le réseau ne se retrouve pas paralysé puisque les autres services se trouvent sur d'autres serveurs qui sont toujours fonctionnels. Ce modèle permet également l'équilibrage de charge ainsi que de la redondance des serveurs. Malheureusement, nous n'avons pas pu expérimenter ces fonctionnalités à cause du manque de matériel et de licences de plus haut niveau de VMware vSphere.

Comme vous pouvez le remarquer, nous avons inclus deux topologies :

- Topologie idéale
- Topologie réelle

La topologie idéale présente la topologie que l'on voit normalement dans une petite entreprise. Un seul hôte VMware opère toutes les machines virtuelles. Cet hôte est généralement un serveur pourvu de matériel de type *server-grade* avec beaucoup de mémoire vive et une solution de stockage performante. Malheureusement, nous ne sommes pas équipés avec du tel matériel pour faire nos laboratoires. C'est pourquoi la topologie réelle est introduite. Cette topologie est la topologie réseau utilisée pour notre laboratoire. Après avoir monté quelques machines virtuelles, l'hôte ESXi se trouvait grandement limité en terme de performances. Notre hôte n'était équipé que de 8 GB de mémoire vive. Or, c'est cette ressource qui est la plus importante en virtualisation. De plus, l'hôte n'avait qu'un seul disque dur 5400 RPM alors que nous retrouvons le plus souvent en entreprise des disques durs 10K voir 15K RPM assemblés en RAID 10 afin d'augmenter le nombre d'IOPS. À cause de ces deux facteurs, nous avons dû diviser la charge de travail (*workload*) en deux hôtes : le serveur VMware ESXi 5.5 accompagné d'une machine cliente virtualisant deux autres machines virtuelles avec le logiciel VMware Workstation 10. Avec cette topologie, nous étions donc capables de virtualiser toutes les machines nécessaires au réseau.

Tout comme le Projet 1, nous utiliserons pfSense afin de connecter notre réseau privé au réseau du collège Montmorency ainsi qu'à Internet.

Dans le cadre du serveur de déploiement, nous avons également décidé d'inclure le service Windows Server Update Services. Ce serveur virtuel pourra donc déployer les mises à jour disponibles sur Windows Update aux machines Windows sur le réseau.

Tâches réalisées

Création d'un serveur de déploiement Microsoft

Le service de déploiement Microsoft est une technologie implantée dans toutes les versions de Windows Server depuis la version 2003 SP2. Ce service est le successeur de Remote Installation Service présent dans Windows Server 2000. Il permet notamment de déployer des images d'un système Windows sur des machines en réseau via PXE (Preboot Execution Environment). Le service permet également de capturer intégralement des postes de machines clientes afin de les redéployer ultérieurement.

Le service est relativement léger dans son opération au niveau mémoire vive et processeur. Il est toutefois gourmand en ressources disque et réseau. Les images capturées prennent beaucoup d'espace disque. Heureusement, les différentes versions de Windows sont toutes livrées sur le même disque d'installation. De ce fait, une seule image est nécessaire pour installer toutes les versions de Windows 7, de même que Windows 8. Au niveau des composants réseau, le serveur se doit d'être câblé sur un réseau Gigabit pour délivrer des performances acceptables lors de déploiements ou de captures d'images systèmes.

Paramètre	Réglage
Hardware Compatibility	Workstation/ESXi 10.0
CPU	4 Cores, no HT
RAM	2 GB
HDD	60 GB*, LSI Logic SAS, SCSI
Network Adapter	Bridged, connected directly to physical network. Connected at power on.
Virtualized Operating System	Microsoft Windows Server 2012 R2 Update 1

Voici la configuration de la machine virtuelle SRV2012R2-Deployment :

* Nous avons configuré la machine virtuelle avec un disque dur virtuel de 60 GB seulement à des fins de laboratoire. Dans un environnement de production, il faudra compter sur beaucoup plus d'espace disque si l'on veut capturer beaucoup de postes et si l'on veut supporter plusieurs versions du système d'exploitation Microsoft Windows.

Partie 1 : Windows Server Update Services

- 1. À partir du Server Manager, installez le rôle Windows Server Update Services et Windows Deployment Services.
 - a) Sélectionnez les rôles dans la fenêtre de sélection.



b) Dans la fenêtre de sélection des fonctionnalités, appuyez sur Next.



c) Dans la fenêtre WSUS, appuyez sur Next.



d) Dans la fenêtre **Role Services**, s'assurer que **WID Database** et **WSUS Services** sont cochés.



e) Choisissez un emplacement pour y stocker les mises à jour.



f) Dans la fenêtre Web Server Role (IIS), cliquez sur Next.



g) Dans la fenêtre Role Services, cliquez sur Next.



h) **Confirmer** l'installation en cliquant sur **Install**.



i) Une fois l'installation terminée, appuyez sur Close.



 Complétez la post-installation de Windows Server Update Services en ouvrant pour la première fois le service via le panneau WSUS dans Server Manager. Cliquez sur Run. Une fois complétée, cliquez sur Close.



b	Complete WSUS Installation	x		
	Post-installation successfully completed. Click Close to launch the WSUS Administration Console.			
Stor Co	e updates locally ntent directory path: C:\Comsys WSUS	Browse		
	Run	Close		

- 3. Complétez la configuration du service Windows Server Update Services en suivant les étapes ci-dessous.
 - a) Cliquer sur **Next** pour démarrer la configuration.

3 Windows	s Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9
 Windows Before You Begin Things you shoul Before You Begin Things you shoul Before You Begin Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages 	 s Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9 Id do before starting this wizard Before you begin: Is the server firewall configured to allow clients to access the server? Can this computer connect to the upstream server (such as Microsoft Update)? Do you have user credentials for the proxy server, if needed?
Choose Products Choose Classifications Configure Sync Schedule Finished What's Next	To run this wizard again, launch the WSUS Administration Snap-in and go to Options
	< Back Next > Finish Cancel

b) Cochez la case pour joindre le programme d'amélioration de Microsoft si désiré.



c) Synchronisez le service local avec le service **Windows Update**. Cliquez ensuite sur **Next.**

b Winde	ows Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9	x
Choose Upstre	eam Server upstream server from which you want to synchronize content	
Before You Begin Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages Choose Products Choose Classifications Configure Sync Schedule Finished What's Next	You can choose the upstream server from which your server synchronizes updates. • Synchronize from Microsoft Update • Synchronize from another Windows Server Update Services server Server name: Port number: 8530 Use SSL when synchronizing update information If using SSL, ensure that the upstream WSUS server is also configured to support SSL. This is a replica of the upstream server A replica server mirrors update approvals, settings, computers and groups from its parent. Updates can be approved only on the upstream server. 	
	< Back Next > Finish Cancel	

d) Dans notre cas, aucun proxy n'a dû être configuré. Cliquez sur **Next**.

b Wind	lows Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9	x
Specify Proxy Provide proxy	r Server sy server settings for synchronizing updates with Microsoft Update	
Before You Begin Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages Choose Products Choose Classifications Configure Sync Schedule Finished What's Next	If this server requires a proxy server to access the upstream server, you can configure the proxy server settings here. Use a proxy server when synchronizing Proxy server name: Port number: 80 Use user credentials to connect to the proxy server User name: Domain: Password: Allow basic authentication (password is sent in cleartext)	
	< Back Next > Finish Cancel	

e) Choisir la **langue** des mises à jour. Celle-ci doit correspondre avec la langue des machines clientes installées sur le réseau.

🐌 Windo	vs Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9		
Choose Languages Select the languages for which this server will download updates			
Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages Choose Products	 Provide the storing update files locally, you can filter the updates downloaded to your server by language. Choosing individual languages will affect which computers can be updated on this server and any downstream servers. Download updates in all languages, including new languages Download updates only in these languages: 		
Choose Classifications Configure Sync Schedule Finished What's Next	□ Arabic □ French □ Norwegian □ Bulgarian □ German □ Polish □ Chinese (Hong Kong S.A.R.) □ Greek □ Portuguese □ Chinese (Simplified) □ Hebrew □ Portuguese □ Chinese (Traditional) □ Hindi □ Romanian □ Croatian □ Hungarian □ Russian □ Czech □ Italian □ Serbian (Lati □ Danish □ Japanese □ Slovak □ Dutch □ Japanese (NEC) □ Slovenian □ Estonian □ Latvian □ Swedish □ Finnish □ Lithuanian □ Thai		
	< Back Next > Finish Cancel		

f) Choisissez les produits Microsoft qui seront tenus à jour. Normalement, on sélectionne seulement les versions des systèmes d'exploitation des machines clientes ainsi que les logiciels installés sur celles-ci.



g) Sélectionnez toutes les classifications de mises à jour.

🐌 Winde	ows Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9
Choose Classi Select the up Before You Begin	fications date classifications you want to download You can specify what classification of updates you want to synchronize.
Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages Choose Products Choose Classifications Configure Sync Schedule Finished What's Next	 Classifications: All Classifications Critical Updates Definition Updates Preature Packs Security Updates Service Packs Tools Update Rollups Updates
	All classifications, including classifications that are added in the future.
	< Back Next > Finish Cancel

 h) Synchronisez automatiquement les mises à jour de façon périodique ou manuellement. Cochez l'option désirée puis cliquez sur Next.

南	Windows Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9
Set Sync Scher Configure wh	dule nen this server synchronizes with Microsoft Update
Before You Begin Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages Choose Products Choose Classifications Configure Sync Schedule Finished What's Next	 Synchronize updates manually or set a schedule for daily automatic synchronization. Synchronize manually Synchronize automatically First synchronization: 8:57:17 PM Synchronizations per day: Note that when scheduling a daily synchronization from Microsoft Update, the synchronization start time will have a random offset up to 30 minutes after the specified time.
	< Back Next > Finish Cancel

i) Cocher la case **Begin initial synchronization**. Appuyez ensuite sur **Next**.



j) L'utilitaire de configuration vous propose ensuite de configurer des options supplémentaires. Une option intéressante serait la première, qui propose de configurer un certificat SSL pour le service WSUS. Un certificat SSL authentifierait le serveur de mise à jour sur le réseau. De cette manière, les machines clientes pourraient vérifier l'authenticité des mises à jour, éliminant tout risque d'installation et de propagation de mises à jour frauduleuse issues d'un autre serveur provenant d'un pirate. La deuxième option permet de créer des groupes d'ordinateurs pour regrouper des postes sur un réseau. La troisième permet de créer des groupes de machines via la stratégie de groupe. Finalement, la quatrième permet de configurer des règles d'approbation automatique. Cliquez sur **Finish**.

🐌 Winde	ows Server Update Services Configuration Wizard:WIN-V6N9PFH2JC9
What's Next Next steps to	get your WSUS Server integrated into your environment
Before You Begin Microsoft Update Improvement Program Choose Upstream Server Specify Proxy Server Choose Languages Choose Products Choose Classifications Configure Sync Schedule Finished What's Next	 Next Steps: To fully configure your system, you should explore the following topics: 1. <u>Using SSL with WSUS</u> 2. <u>Create computer groups</u> 3. <u>Assign computers to groups using Group Policy</u> 4. <u>Configure auto-approval rules</u>
	< Back Next > Finish Cancel

4. Allez dans les Administrative Tools. Cliquez sur Windows Server Update Services. La console Update Services s'affichera.



Le serveur de déploiement de mises à jour est désormais prêt à l'utilisation. Cependant, aucun ordinateur n'est encore affecté au serveur. Normalement, un serveur WSUS se fait dans un environnement où un contrôleur de domaine ainsi qu'un *Active Directory* sont en place. Dans un tel environnement, on applique via une stratégie de groupe (*Group Policy*) la stratégie «*Specify intranet Microsoft Update Service location*» et on spécifie dans les paramètres de celle-ci l'adresse du serveur WSUS. Cette méthode active le *client-side targeting*.

5. Pour ajouter des ordinateurs au serveur de déploiement de mises à jours, il faut aller dans le menu **Option** et cliquer sur **Computers**.



6. Sélectionnez l'option **Use Group Policy or registry settings on computers**. Cliquez sur **Apply** et sur **OK**.

	Computers	x
General]	
\$	You can specify how to assign computers to groups.	
O Use	the Update Services <u>c</u> onsole	
No Co	te: New computers will automatically be placed in the Unassigned mputers group.	
O Use	Group Policy or registry settings on computers.	
	OK Cancel <u>A</u> pply	′

7. Il faut ensuite créer un nouveau groupe d'ordinateurs clients. Cliquez droit sur All Computers et cliquez sur Add Computer Group...

📷 📷 File Action View Window	/ Help	Update	Services				
🗢 🄿 🙎 🖬 👔							
Update Services All Computers (0 computers of 0 shown, 0 total)						Ac	tions
SRV2012R2-DEPLOYMENT Status: Failed or Needed • Q Refresh				AI	I Computers		
⊿ 💕 Computers	① Name	IP Address	Operating System	Inst	Last Status Report	<u>م</u>	Search
All Comp Search	h						Add Computer Group
Downstream Add C	Computer Group						View 🕨
synchronizat View	•						New Window from Here
Reports New \ Options	Window from Here					٥	Refresh
Refres	sh					?	Help
Help							
< <u>111</u> >	There are no items selected						
						• 9	ENG 11:00 AM

8. Donnez un nom à votre groupe d'ordinateurs clients. Cliquez ensuite sur Add.

	Add Computer Group	x
\$	Specify a name for the new computer group.	
	Name: ComSystem Laptops Name: ComSystem Laptops Add Cancel	

9. Une fois que nous avons ajouté un groupe d'ordinateurs clients, nous avons maintenant besoin de créer une nouvelle stratégie de groupe (GPO) et de configurer celle-ci de sorte que les clients du domaine soient affectés par cette nouvelle GPO.

Sur le contrôleur de domaine (DC), dans le **Group Policy Management Editor**, éditez la politique locale. Cliquez droit sur cette dernière et cliquez sur **Create a GPU in this domain, and Link it here...**



10. Donnez un nom à la nouvelle GPO.

		Group Po	olicy Management				C) X		
😹 File Action View Window Help								_ 8 ×		
<table-cell-rows> 🔿 🙍 📋 🗶 🛱 🗖</table-cell-rows>										
Group Policy Management	ComSystem Laptop									
A B Domains	Linked	Group Policy Objects	Group Policy Inheritance Dele	egation						
∠ iii Comsvs.local		LinkOrder	GPO	Enforced	Link Enabled	GPO Status	WMI Filter	Moc		
📓 Comsys Infra Standard		1	🛒 ComSystem Software Co	No	Yes	Enabled	None	8/8.		
ComSystem IE Restrictions										
Default Domain Policy										
ComSystem Laptop										
Domain Controllers	$ \ge$									
D II HR										
Marketing			New GPO	x						
Production	-									
Research	Name:									
Group Policy Objects	WSUS ComSystem Laptop									
WMI Filters										
Image: Starter GPOs	Source Starter GPO:									
Sites	(none)									
Group Policy Modeling			OK	Canaal						
				Cancel						
					-					
		<		Ш				>		
🕂 占 🛛 👸 🐌	I					F	5 12 (b 8	2:05 AM /19/2013		

11. Cliquez droit sur la nouvelle GPO et cochez la case Link Enabled. Appuyez ensuite sur Edit.

📓 Group Policy Management						_ 0 ×	
📓 File Action View Window Help							_ 8 ×
🗢 🔿 🙍 📰 🗙 🧟							
Group Policy Management	NSUS ComSystem Laptop						
⊿ 🙀 Domains		Links					
Comsys.iocal		Display links in this locati	~				
ComSystem IE Restrictions		The following sites, domains, and OUs are linked to this GPO:					
Default Domain Policy		Location		Enforced	Link Enabled	Path	
ComSystem Laptop	ontrol GPO	ComSystem Laptop		No	Yes	Comsys.local/ComSystem Laptor	
🛒 WSUS ComSystem Lapt	Edit		1				
Domain Controllers	Enforced						
	✓ Link Enab	led					
Marketing	Save Repo	ort					
▷ Droduction	View	•			Ш		
Research Group Policy Objects	New Wind	low from Here					
WMI Filters	Delete						
Starter GPOs	Rename		can only apply to the folio	wing groups, use	ers, and computers:		
Group Policy Modeling	Refresh						
Group Policy Results	Help						
		Add	Remove	Properties			
	WMI Filtering This GPO is linked to the following WMI filter: <pre></pre> <pre></pre> <pre>Open</pre>						
Open the GPO editor		L					
	16 4						12:06 AM
						18 E	8/19/2013

12. Toujours dans le *Group Policy Management Editor*, sous **Computer Configuration**, doublecliquez sur **Policies**, **Administrative Templates**, **Windows Components**, et cliquez sur **Windows Update**.

<u>s</u>	Group Policy Management Editor	_	0	ĸ
File Action View Help				
🗢 🔿 🙍 🖬 🔒 🛛 🗊 🛛 🝸				
WSUS ComSystem Laptop [DC01.COMSYS.LO ^	Setting State Comment			^
4 🐏 Computer Configuration	🚆 Remote Desktop Services			
⊿ 🧮 Policies	RSS Feeds			
Software Settings	🔁 Security Center			
Windows Settings	Server for NIS			
A Administrative Templates: Policy de la construcción	Gamma Shutdown Options			
Control Panel	SkyDrive			
▷ iii Network	Smart Card			
Printers	Sound Recorder			
Server	Sync your settings			
Start Menu and Taskbar				
System	Task Scheduler			
△ Windows Components	Windows Calendar			
ActiveX Installer Service				
Add features to Windows 8.	Windows Customer Experience Improvement Program			
App Package Deployment	Windows Defender			
App runtime	Windows Bereiden			
AutoDisc Delicies				
Piometrics	Windows Installer			
Biometrics	Windows Logon Options			
Credential User Interface				
Deckton Gadgets	Windows Media Center			
Desktop Gaugets	Windows Media Digital Rights Management			
Device and Driver Compatib	Windows Media Player			
Digital Locker	Windows Messenger			≡
Event Forwarding	Windows Mobility Center			
Event Log Service	Windows PowerShell			
Fvent Viewer	Windows Reliability Analysis			
Eamily Safety	📔 Windows Remote Management (WinRM)			
▷ ☐ File Explorer	Windows Remote Shell			
File History	📓 Windows Update			
Game Explorer	Work Folders			
HomeGroup				\sim
< III >	Extended Standard			
			12:10 AI	м
		H 10	8/19/20	13

13. Dans la fenêtre des paramètres de la GPO, double-cliquez sur **Configure Automatic Updates**, et cliquez par la suite sur **Enabled**. Sous le menu **Options**, dans **Configure automatic updating**, sélectionnez l'option 3 : **Auto download and notify for install**, et cliquez sur **Apply** puis sur **OK**.


14. Cliquez sur la prochaine GPO, soit Specify intranet Microsoft update service location. Dans le menu des réglages, sélectionnez l'option Enabled. Spécifiez ensuite l'URL du serveur WSUS. N'oubliez pas d'ajouter le port 8530 à la fin de l'URL.



15. Dans la GPO suivante, soit **Enable client-side targeting,** cochez l'option **Enabled**. Dans le champ **Target group name for this computer**, entrez le nom du groupe préalablement créé. **Cliquez sur Apply**, puis sur **OK**.



16. Sur la machine cliente, après avoir effectué la commande gpupdate /force pour mettre à jour la stratégie de groupe sur le poste, on peut effectuer la commande gpresult /r pour voir si le client a bien reçu les GPO. Sous COMPUTER SETTINGS, Applied Group Policy Objects, vous retrouverez une ligne WSUS avec le groupe d'ordinateur WSUS auquel la machine cliente appartient.



17. Il faut par la suite initialiser Windows Update avec la commande Wuauclt.exe /reportnow /detectnow.



18. Sur le serveur WSUS, il faut approuver les mises à jour pour les PC clients. Dans la **console WSUS**, sous **Updates**, cliquez sur les catégories de mises à jour et approuvez celles-ci en cliquant droit et en cliquant sur **Approve**.

声		Update S	ervice	s			_ 0 ×
🚡 File Action View Window	Help						_ 8 ×
🗢 🄿 🙍 🖬 🚺 🖬							
by Update Services	Critical Updates (95 updates of 97 sho	wn, 97 total)					Actions
⊿ 👼 DC01 ⊿ 🐺 Updates	Approval: Any Except Declined - Statu	us: Any	-	🔉 Refresl	h		Critical Updates
All Updates	1 Title			1	nstalle Approval	^	🔎 Search
😽 Critical Updates	Update for Windows 8 (KB2751352)				0% Declined	_	😽 New Update View
Security Updates	Update for Windows 8 (KB28128			1	0% Not approved		View 🕨
WSUS Updates	Update for Windows Server 2012	Approve			0% Not approved		New Window from Here
A NI Computers	Update for Internet Explorer Flas	Decline		sed	0% Not approved		Refrech
🕵 Unassigned Com	Update for Internet Explorer Flas	Group By	•	ised	0% Not approved		
💕 ComSystem Lapti	Update for Internet Explorer Flas	Revision History		72)	0% Not approved		Минер
Downstream Servers	Update for Internet Explorer Flas	File Information		(KB2	0% Not approved		Update 🔺
Reports	Update for Internet Explorer Flas	Status Report		ised	0% Not approved		approve
Dptions	Update for Internet Explorer Flas	Help		(KB2	0% Not approved		👼 Decline
	Update for Windows 8 for x64-based Systems (KB2812822) 0% Not approved						🖫 Group By
	Update for Internet Explorer Flash Play	ver for Windows 8 (I	(B28059	40)	0% Not approved		Revision History
	Update for Internet Explorer Flash Player for Windows Server 2012 (KB2 0% Not approved				File Information		
	Update for Internet Explorer Flash Player for Windows Server 2012 (KB2 0% Not approved					Status Papart	
	Update for Windows 8 for x64-based Systems (KB2803748) 0% Not approved						
	Update for Windows 8 (KB2803748) 0% Not approved			~	I Help		
	Update for Windows 8 (KB2812822)						
						_	
	This update is superseded by anothe you verify it is no longer needed by a	er update. Before yo any computers. To e	u declir do so, a	ie any sup pprove the	erseded update, we recommend that e superseding update first.	Ĥ	
	Status:		MSR	`severity	v. Unspecified	≡	
	Computers with errors:	0	MSRO	numbe	r: None		
	Computers needing this update: 0 Release date: Wednesday, March 13,						
	Computers installed/hot	is: 0			2013		
			KB ar	ticle nur	nbers: 2812822		
	Description						
< III >	Install this update to resolve issues in W	indows. For a com	olete list	ina of the	issues that are included in this	~	
Approve selected updates							
							1:41 AM 8/19/2013

19. Dans la fenêtre **Approve Update**, cliquez sur le groupe d'ordinateurs et sélectionnez **Approved for install. Cliquez** ensuite sur **OK** puis sur **Close**.



Approve Updates				
To approve an update, select the of approval.	e group from this list of gro	ups, click the arrow, and choose the type		
Computer Group	Approval	Deadline		
🚫 🗹 All Computers	Not approved	N/A		
🚫 🏹 Unassigned Computers	Not approved (inherited)	N/A (inherited)		
🕢 🍸 ComSystem Laptop	Install	None		
		OK Cancel		

	Approval Progress	X
Approval completed	without errors. See below for details.	
Action	Result Result Success	
Approving Updat	e for Windows 8 (KB2812822) for installation to ComSystem Laptop Success	
	Pause Cancel Close	

20. Les mises à jour se téléchargeront sur le serveur.



21. Une fois le téléchargement terminé, les mises à jour apparaîtront dans la console Windows Update de l'ordinateur client. **Sélectionnez la mise à jour et cliquez sur Install.**



22. La machine cliente installera les mises à jour à partir du serveur WSUS.



WSUS via le registre Windows

Pour en connaître davantage sur les paramètres requis pour distribuer les mises à jour Windows via des réglages dans le registre, veuillez consulter cette page : http://technet.microsoft.com/en-us/library/dd939844(v=ws.10).aspx

Partie 2 : Windows Deployment Service

1. Le rôle **Windows Deployment Services** étant déjà installé dans la partie 1, allez dans le **Server Manager**, allez dans le rôle **WDS**, puis cliquez droit sur le serveur local. Sélectionnez **Windows Deployment Services Management Console.**

B		Server Manager		_ 0 ×
Server Ma	nager • WDS	•	C 🍢 Manage Iools	: <u>V</u> iew <u>H</u> elp
 Dashboard Local Server All Servers File and Storage Services 	SERVERS All servers 1 total	P (⊞ ▼ (R) ▼	Last Undate Windows Activ	
 IIS WDS Windows Server Essenti WSUS 	SRV2012R2-DEPLO 10.0	Add Roles and Features Shut Down Local Server Computer Management Remote Desktop Connection Windows PowerShell Configure NIC Teaming	3:04 PM 00253-50000-0	p0000-AA785 (A
	EVENTS All events 18 total Filter	Configure Windows Automatic Feedback Windows Deployment Services Management Co Manage As Start Performance Counters Refresh	insole	TASKS V
	Server Name ID Server Name SRV2012R2-DEPLO 772 Err SRV2012R2-DEPLO 772 Err	Copy verity Source or WDSServer III	Log Application Application Application Application Application Application	
			× 🔁 🕼	ENG 3:53 PM US 2014-05-03

2. Le serveur n'est pas configuré. Il faut donc cliquer droit sur SRV2012R2-Deployment (ou le nom de votre serveur) puis cliquer sur **Configure Server.**

<u>e</u>	Windows Deployment Services	-	- 0 ×
File Action View Help			
🗢 🄿 🙍 🖬 🔍 🖬			
🝨 Windows Deployment Services	s SRV2012R2-Deployment		
⊿ III Servers			
SRV2012R2-Deployment Active Directory Presta	Configure Server pws Deployment Services is not configured		
	Remove Server		
	View to configured. To configure this server, right-click the server, and then click Configure Server.		
	Refresh		
	Help		
Configures this convertes the first we			
Configures this server for the first us	J35.		
	🔁 🖕 🔹 🔸	🗜 🕼 ENG US	2:38 PM 2014-05-03

3. La page de départ de la configuration du serveur s'affichera. Cliquez sur Next.

Windows Deployment Services Configuration Wizard	x
Before You Begin	
You can use this wizard to configure Windows Deployment Services. Once the server is configured, you will need to add at least one boot image and one install image to the server before you will be able to install an operating system.	
Before you begin, ensure that the following requirements are met:	
 The server is a member of an Active Directory Domain Services (AD DS) domain, or a domain controller for an AD DS domain. If the server supports Standalone mode, it can be configured without having a dependency on Active Directory. 	
 There is an active DHCP server on the network. This is because Windows Deployment Services uses Pre-Boot Execution Environment (PXE), which relies on DHCP for IP addressing. 	
 There is an active DNS server on your network. 	
 This server has an NTFS file system partition on which to store images. 	
To continue, click Next.	
< Back Next >	Cancel

4. Puisque le serveur est installé dans un environnement où *Active Directory* n'est pas implémenté, sélectionnez **Standalone Server**.

Windows Deployment Services Configuration Wizard	x
Install Options	
Select one of the following options:	
This server is a member of an Active Directory Domain Services (AD DS) domain, or a domain controller for an AD DS domain.	
Configure the server so that it is standalone, operating independently of Active Directory.	
< <u>B</u> ack <u>N</u> ext >	Cancel

 Sélectionnez un dossier où les installations distantes seront effectuées. Ici, le chemin est C:\Deployment. Appuyez ensuite sur Next.

Windows Deployment Services Configuration Wi	zard ×
Remote Installation Folder Location	
The remote installation folder will contain boot images, install images, PXE boot files, and the Windows Deployment Services management tools. Choose a partition that is large enough to hold all of the images that you will have. This partition must be an NTFS partition and should not be the system partition.	,
Enter the path to the remote installation folder.	
Path:	
C:\Deployment Browse	
< <u>B</u> ack	Next > Cancel

6. Une fenêtre d'avertissement apparaîtra. Elle souligne le fait que le dossier est situé sur le même disque que celui où le système est installé et qu'une telle configuration pourrait diminuer les performances. Dans notre cas, cela nous importe peu puisque nous sommes dans une machine dédiée aux déploiements, qui plus est une machine virtuelle. Cliquez sur **Yes**.

	System Volume Warning	x
<u>^</u>	The volume selected is also the Windows system volume. For best performance and data reliability, the remote installation folder should be stored on a separate volume, and, where possible, on a separate disk from the system volume. Do you want to continue?	
	<u>Y</u> es <u>N</u> o	

7. La prochaine fenêtre explique le fonctionnement du PXE. Cochez la case **Respond to all client computers (known and unkown)** de sorte que le serveur PXE puisse répondre aux ordinateurs sur le réseau démarrant sur leur adaptateur réseau. Cela inclut une brèche de sécurité puisque n'importe quelle machine sur le réseau sera acceptée par le serveur, y compris les machines inconnues du serveur. Appuyez ensuite sur **Next**.

windows Deployment Services Configuration Wizard 🗙
PXE Server Initial Settings
You can use these settings to define which client computers this server will respond to. Known clients are the clients that have been prestaged. When the physical computer performs a PXE boot, the operating system will be installed based on the settings that you have defined.
Select one of the following options:
O Do not respond to any client computers
O Respond only to <u>k</u> nown client computers
Respond to all client computers (known and unknown)
Reguire administrator approval for unknown computers. When you select this option, you must approve the computers using the Pending Devices node in the snap-in. Approved computers will be added to the list of prestaged clients.
To configure this server, click Next.
< <u>B</u> ack <u>N</u> ext > Cancel

8. Une fenêtre montrant la progression de la configuration du serveur s'affichera.

Windows Deployment Services Config	guration Wizard 🛛 🗙
Task Progress	
Configuring Windows Deployment Services	
Starting Windows Deployment Services	
	< Back Finish Cancel

9. Une fois l'opération complétée, l'assistant de configuration vous demandera si vous souhaitez ajouter des images au serveur de déploiement. Assurez-vous que la case Add images to thé server now est bien cochée, puis cliquez sur Finish.

windows Deployment Services Configuration Wizard	×
Operation Complete	
You have successfully configured Windows Deployment Services. To modify any of the server settings, right-click the server, and click Properties.	
Now that you have configured the server, you will need to add images. These images include a boo image (which is the bootable environment that you initially boot the computer into), and the install images (which are the operating system images that you deploy).	t
To add images when this wizard closes, select the following check box. To add images at a later tim right-click the Install Images or Boot Images node in the snap-in.	ie,
▲ Add images to the server now	
To close this wizard, click Finish.	
< <u>B</u> ack Finish	Cancel

10. Dans le dossier **C:\Deployment**, créez un dossier nommé **ISO**. Ce dossier contiendra les fichiers ISO requis pour les installations.

🎉 💽 🚺 = I	Deploymer	nt			x I
File Home Share	View				~ ?
🔄 🏵 🔻 🕆 🚺 🕨 Thi	s PC 🔸 Local Disk (C:) 🔸 Deployment 🕨	~ ¢	Search Deploy	ment	Q
👉 Favorites	Name	Date modified	Туре	Size	
Desktop	3 Boot	2014-05-03 2:43 PM	File folder		
Downloads	📕 Images	2014-05-03 2:43 PM	File folder		
🖫 Recent places	🔒 ISO	2014-05-03 2:44 PM	File folder		
	퉬 Mgmt	2014-05-03 2:43 PM	File folder		_
👰 This PC	퉬 Stores	2014-05-03 2:43 PM	File folder		
	퉬 Templates	2014-05-03 2:43 PM	File folder		
👊 Network	鷆 Tmp	2014-05-03 2:43 PM	File folder		
	퉬 WdsClientUnattend	2014-05-03 2:43 PM	File folder		
8 items 1 item selected					:==

11. **Copiez** un fichier ISO d'un système d'exploitation Windows. Dans le cas présent, il s'agit d'une image disque de Windows 8.1 Enterprise with Update (x64) - English.



12. Une fois le fichier ISO copié dans le dossier, **décompressez-le** avec un utilitaire tel que *WinRAR* ou *7ZIP*.

👪 l 💽 🚯 = l		Disc Image Tools		ISO			x		
File Home Share	View	Manage					~ ()		
🔄 🍥 👻 🕆 🌗 🕨 Thi	s PC ▶ Loca	l Disk (C:) 🕨 Dep	oyment 🕨 ISO	~ ¢	, Search ISO		٩		
☆ Favorites ■ Desktop	Name	dows_8.1_enterpris	e_with_update	Date modified 2014-04-27 6:00 PM	Type Disc Image File	Size 3,863,244 KB			
🐌 Downloads 🗐 Recent places		 Mount Open with Add to archi 	/e				r		
🖳 This PC		Add to "en_v	vindows_8.1_enter	prise_with_update_x64_0	dvd_4065178.rar"				
🗣 Network	Add to "en_windows_8.1_enterprise_with_update_xb4_dvd_40b5178.rar" Compress and email Compress to "en_windows_8.1erprise_with_update_x64_dvd_4065178.rar" and email Extract files Extract Here Extract to en_windows_8.1_enterprise_with_update_x64_dvd_4065178\ Restore previous versions Send to Cut								
		Create short Delete Rename Properties	:ut						
1 item 1 item selected 3.6	58 GB								

Dans la fenêtre Add Image Wizard, sélectionnez le dossier C:\Deployment\ISO\[nom du dossier de l'image]\sources. Ce dossier contient tous les fichiers de démarrage requis. Appuyez sur Next.

1	Add Image Wizard	x
	Image File	
	Enter the path to the root of the installation DVD which contains the images that you want to add. This location must contain the default boot and install images (Boot.wim and Install.wim). It cannot contain a custom image.	
	Path: windows_8.1_enterprise_with_update_x64_dvd_4065178\sources Browse	
	< <u>B</u> ack <u>N</u> ext > Canc	el

14. L'assistant d'ajout d'images vous demandera de créer un groupe d'images. Normalement, on regroupe les images par version de système d'exploitation de sorte à faciliter la gestion. **Créez un nom de groupe d'images** et appuyez sur **Next.**

4	Add Image	e Wizard 🛛 🗙
	Image Group	
	This wizard adds an install image to your serve image and one boot image on your server in or Execution Environment (PXE) and install an ope	er. You must have at least one install rder to boot a client using Pre-Boot erating system.
	An image group is a collection of images that s security. Enter the image group for the install i	hare common file resources and image that you want to add.
	O Select an <u>e</u> xisting image group	~
	<u>C</u> reate an image group named Wir	ndows-8.1-Update
		< <u>B</u> ack <u>N</u> ext > Cancel

15. La fenêtre de résumé des paramètres s'affichera. Appuyez sur Next.

*	Add Image Wizard
Review Settings	
Verify that the following info	ormation is correct.
Image path:	_enterprise_with_update_x64_dvd_4065178\sources
Install image group:	Windows-8.1-Update
Number of install images:	1
Number of boot images:	1
To make changes, dick Back	. To add the selected images to the server, dick Next.
	< <u>B</u> ack <u>N</u> ext > Cancel

16. Le serveur ajoutera les images et vérifiera l'intégrité de celles-ci.

4	Add Image Wizard	X
Task Progress		
Adding boot image		
Adding Image 1 of 1 (N	/icrosoft Windows Setup (x64))	
	< <u>B</u> ack Finish	Cancel

17. L'opération est réussie lorsque cette fenêtre apparait. Appuyez sur Finish.

<u>1</u>	Add Image Wizard	x
Task P	rogress	
The	operation is complete	
The	enterted impress were successfully added to the conver	
Ine	selected images were successfully added to the server.	
	< <u>B</u> ack Finish	Cancel

18. Dans la console *Windows Deployment Services*, vérifiez si les images d'installation et de démarrage ont bel et bien été ajoutées correctement.

<u>4</u>		Windows De	eployme	nt Services				- 0	x
<u>File Action View H</u> elp									
🗢 🔿 🙍 📰 📑					_				
🝨 Windows Deployment Services	Windows-8.1-Update 1 Ir	nstall Image(s)							
 Servers Servers SRV2012R2-Deployment Install Images Windows-8.1-Update Boot Images Pending Devices Prestaged Devices Multicast Transmissions Active Directory Prestaged Devices 	Image Name	Architecture x64	Status Online	Expanded Size 12023 MB	Date 2014	OS Version 6.3.9600	Priority 500000		

Windows Deployment Services								- C	ז	x
<u>File Action View H</u> elp										
🗢 🔿 🙍 📰 📑 🚺					_					
🝨 Windows Deployment Services	Boot Images 1 Boot Image(s)									
⊿ Servers	Image Name	Architecture	Status	Expanded Size	Date	OS Version	Priority			
 SRV2012R2-Deployment Install Images Boot Images Boot Images Perstaged Devices Multicast Transmissions Drivers Active Directory Prestaged Devices 	Microsoft Windows Setup (x64)	x64	Online	1198 MB	2014	6.3.9600	500000			

19. Pour tester le serveur, nous nous sommes créé une nouvelle machine virtuelle. Pour faire en sorte que celle-ci démarre sur l'adaptateur réseau virtuel (en l'occurrence, la carte réseau Intel 1000e), il faut entrer dans le BIOS de la machine virtuelle et **modifier l'ordre de démarrage des périphériques.** Sauvegardez le BIOS avec les modifications et redémarrez la machine virtuelle.

Ma	in I	Advar	nced	Phoen i x Secur i ty	kBIOS J	Setup Boot	Utility Exit			
	Networi •Removal •Hard D: CD-ROM	k boc ble I rive Driv	ot from Devices De	Intel E10	000e			Item S Keys use configue <enter> collapse a + or <ctrl+en all <+> and device u <n> May device 1 Disk or <d> Reme that is</d></n></ctrl+en </enter>	Specific Hel ed to view o re devices: expands or es devices w nter> expand <-> moves t up or down. move remova between Hard Removable D ove a device not install	p r ith s ble isk ed.
F1 Esc	Help Exit	1↓ ↔	Select Select	Item -/ Menu En	/+ nter	Change Select	Values ► Sub-M	F9 enu F10	Setup Defa Save and E	ults xit

20. Au redémarrage, la machine virtuelle se connectera au réseau et attendra une adresse IP d'un serveur DHCP fonctionnel sur le réseau. Il faudra appuyer sur **F12** pour continuer le démarrage en mode PXE.

Network boot from Intel E1000e Copyright (C) 2003-2008 VMware, Inc. Copyright (C) 1997-2000 Intel Corporation CLIENT MAC ADDR: 00 0C 29 F0 6A 2B GUID: 564D3905-A43F-6E2E-8188-876390F06A2B CLIENT IP: 10.0.3.172 MASK: 255.255.0 DHCP IP: 10.0.2.2 GATEWAY IP: 10.0.3.1 Downloaded WDSNBP from 10.0.3.109 SRV2012R2-Deployment Press F12 for network service boot -

21. La machine virtuelle téléchargera les fichiers de démarrage requis pour Windows depuis le serveur de déploiement, via le réseau virtuel.

Loading files			
IP: 10.0.3.10	9, File: \Boot\x64\Images\boot.	wim	

22. La console d'installation du système d'exploitation Windows démarrera. Sélectionnez la langue désirée pour poursuivre l'opération et appuyez sur **Next**.

	Windows Setup	
	Windows Deployment Services	
	Locale: English (United States)	
	© 2013 Microsoft Corporation. All rights reserved.	
1 Collecting information	2 Installing Windows	

23. Entrez le mot de passe administrateur du serveur de déploiement pour procéder aux étapes d'installation suivantes.

	Windows Setup
	Windows Deployment Services Connect to SRV2012R2-Deployment Image: Connect to SRV2012R2-Deployment Im
	© 2013 Microsoft Corporation. All rights reserved.
Collecting information	2 Installing Windows

24. Sélectionnez la version de Windows à installer. Appuyez sur **Next**.

	Windows Setup Select the operating system you want to Operating system Windows 8.1 Enterprise	install Language en-US	Architecture	Date modified	<u> </u>	
	Windows Setup Select the operating system you want to Operating system Windows 8.1 Enterprise	install Language en-US	Architecture	Date modified		
2	Gelect the operating system you want to Operating system Windows 8.1 Enterprise	install Language en-US	Architecture	Date modified		
	Operating system Windows 8.1 Enterprise	Language en-US	Architecture	Date modified		
	Windows 8.1 Enterprise	en-US				
			x64	5/3/2014		
	Description					
W	Vindows 8.1 Enterprise					
s G	elect a language to install:					
le l	English 💽				_	
				Next		
ollecting information	talling Windows					

25.	Sélectionnez	la partition sur	laquelle	Windows	devra s'installer.	Appuyez sur Next .
	e one official and the					

	🔏 Windows Setup			
	Where do you want to install Windo	ows?		
	Name	Total size	Free space Type	
	Drive 0 Partition 1: System Reserved	350.0 MB	89.0 MB System	
	Drive 0 Partition 2	59.7 GB	25.0 GB Primary	
	A Refrech		Drive ontions (advanced	4)
	Load driver		Drive options (auvanced	u)
				Next
Collecting information	Installing Windows			

Windows s'installera dans la machine virtuelle depuis le serveur de déploiement.

Partie 3 : Capture d'un poste existant

 Dans le but de diversifier le projet, nous capturerons un poste existant opérant le système d'exploitation Windows 7 Professional SP1 x64. Pour ce faire, il nous faut ajouter une nouvelle image de démarrage, cette fois-ci sur Windows 7 x64. Cliquez droit dans le dossier Boot Images et sélectionnez Add Boot Image....



2. Donnez un nom à l'image de démarrage, en l'occurrence Microsoft Windows 7 Setup (x64).

🔮 🛛 🗛 Add Im	nage Wizard	x
Image Metadata		
Enter a name and description for the foll 'Microsoft Windows Setup (x64)' Image name: Microsoft Windows 7 Setup (x64) Image description: Microsoft Windows 7 Setup (x64) Image architecture: x64	owing image:	
	< <u>B</u> ack <u>N</u> ext >	Cancel

3. La page de résumé de l'image de démarrage s'affichera. Appuyez sur Next.

4		Add Image Wizard				
Su	ummary					
	You have selected	the following images				
	Image group:	Boot Images				
	Image file:	$eq:c:deployment_ISO_en_windows_7_professional_with_sp1_x6$				
	Selected images:					
	Name Microsoft Window	/s 7 Setup (x64)				
	To change your selection, click Back. To add the selected images to the server, click Next.					
		< <u>B</u> ack <u>N</u> ext > Cancel				

4. L'assistant ajoutera l'image de démarrage au service de déploiement.

👙 🛛 🕹 Add Im	nage Wizard	x
Task Progress		
Adding boot image		
Adding Image 1 of 1 (Microsoft Windows	s 7 Setup (x64))	
	< <u>B</u> ack Finish	Cancel

5. Cliquez sur **Finish** lorsque l'assistant vous présentera cette fenêtre.

4	Add Image Wizard	X
Task Progress		
The operation is complete		
The selected images were	successfully added to the server.	
	< <u>B</u> ack Finish	Cancel
Il faut par la suite créer une image de capture à partir de l'image de démarrage de Windows 7.
 Pour ce faire, il faut cliquer droit sur l'image actuelle de Windows 7 et cliquer sur Create Capture Image...



7. **Donnez un nom** à l'image de capture. **Spécifiez** également **le chemin** du fichier .wim où sera stocké la capture du poste.

4	Create Capture Image Wizard
P	Metadata and Location
	This wizard creates a capture image from a boot image, and saves it to the location that you specify. At the end of this wizard, you will have the option to add the image back to the server.
	Enter the following information for this capture image. (Note: You cannot use an x64-based capture image for an x86-based computer.)
	Image na <u>m</u> e:
	Microsoft Windows 7 Capture Setup (x64)
	Image <u>d</u> escription:
	Microsoft Windows 7 Capture Setup (x64)
	Image architecture: x64 Location and file name:
	C:\Deployment\ImageCapture\Capture.wim Browse
	To create this capture image, dick Next. More information about capture images
	< Back Next > Cancel

8. L'assistant créera l'image de capture.

🔮 Create Capture Image Wizard	x
Task Progress	
Creating capture image	
Extracting image from the source image file	
< <u>B</u> ack Finish	Cancel

9. Une fois l'image de capture créée, il faut cocher **Add image to the Windows Deployment Server now** pour que celle-ci entre en activité. Une fois la case cochée, cliquez sur **Finish**.

4	Create Capture Image Wizard	x
Ta	ask Progress	
	The operation is complete	
	The image was created successfully.	
	Select the check box to add this image to the server when the wizard closes.	
	✓ Add image to the Windows Deployment Server now	
	< <u>B</u> ack Finish	Cancel

10. **Effectuez la commande** sysprep /oobe /generalize /shutdown sur la machine à capturer. Assurez-vous d'être dans le dossier C:\Windows\System32\Sysprep avant d'effectuer la commande. Une fois l'opération terminée, la machine s'éteindra.



11. Assurez-vous que l'ordre de démarrage des périphériques de la machine virtuelle à capturer est bien réglé pour démarrer en premier sur l'adaptateur réseau Intel 1000e. Appuyez sur F12 pour démarrer en mode PXE. Vous aurez alors un menu Windows Boot Manager. La première option permet d'installer un système Windows 7 64-bit. La deuxième est l'image de démarrage Windows 8 préalablement créée. La dernière est l'image permettant de démarrer en mode capture. Sélectionnez cette option et appuyez sur Enter.



12. La machine cliente démarrera à partir des fichiers de démarrage disponibles sur le serveur de déploiement.



© Pierre-Luc Delisle et Guillaume Nadeau

13. Une fois les modules Windows de base démarrés, l'assistant de capture démarrera. Appuyez sur **Next.**



14. Spécifiez le volume à capturer. Normalement, il n'y aura qu'un seul volume. Pour vous assurer que c'est le bon volume à capturer, vous pouvez exécuter cmd.exe en appuyant simultanément sur **SHIFT+F10.** Exécutez le programme Diskpart et listez les volumes avec la commande **list volume**.

Spécifiez un nom et une description à l'image capturée. Dans le cas présent, il s'agit d'une installation fraîche de Windows 7. C'est pourquoi nous avons nommé notre image capturée **Clean installe Windows 7 x64 Pro.** Appuyez ensuite sur **Next**.

v se	Findows Deployment Services Image Capture Wizard	<u> </u>
	Directory to Capture	
	Enter the following information for this image. Note that you will only see volumes that contain operating systems that have been prepared with Sysprep. Volume to capture: D:\ Image name: Clean install Windows 7 x64 Pro Image description: Clean install Windows 7 x64 Pro	
-	< Back Next > Cancel	

15. En premier lieu, spécifiez un emplacement pour stocker localement la capture du poste. Cela permettra d'éviter les erreurs de transfert et la corruption de l'image lors du téléchargement de celle-ci vers le serveur de déploiement. **Cliquez sur Browse...**

Windows Deployment Services Image Capture Wizard	
New Image Location	
image is not corrupted if there is a network malfunction.	
Browse	
Upload image to a Windows Deployment Services server (optional) Server name:	
Image Group name:	×+.
To create this image, click Next.	
< Back Next > Cancel	

16. À la racine du disque dur, créez un dossier nommé **Image**. Ouvrez le dossier et spécifiez comme nom de fichier **CaptureImage**. Cliquez sur **Save**.

Wi	idows Deployn	nent Services Image Capture Wizard	X	X
	Save in:	Local Disk (D:)		
		Name		
	4 .	Perflogs	7/13/2009 7:20 PM Eile folder	
		Program Files	5/3/2014 1:05 PM File folder	
	Recent Maces	Program Files (v86)	7/13/2009 8:57 PM File folder	
		Ilsers	5/3/2014 12:05 PM File folder	
	Librariae	Windows	5/3/2014 1:10 PM File folder	
	Libraries	Image	5/3/2014 5:17 PM File folder	
		Image: Save as type:	Op Car	en Icel
_				

Windows Deploymer	nt Services Im	age Capture Wizard		>	<u><</u>	
Save As					×	
Save in: 🚺	lmage		- 3 💋	i 📂 🖽 -		
Recent Places Libraries Computer	ame A	This fold	♥ Date modified der is empty.	▼ Type		*
File	e name:	CapturedImage		L	Save	1/
Sa	ive as type:	1		_	Cancel	

17. Entrez le nom du serveur dans la case **Server Name**. Dans le cas présent, il s'agit de SRV2012R2-Depl2. Appuyez sur **Connect**. Vous aurez à rentrer le nom d'utilisateur administrateur du serveur ainsi que le mot de passe de cet utilisateur.

Windows Deployment Services Image Capture Wizard	
Enter a local location where you want to save the install image. This ensures the Windows Security	× ·
< Back Next > Cancel	

Choisissez un groupe d'images. Nous avons choisi le groupe Windows 7 SP1 x64.
 Une fois tous les renseignements rentrés, cliquez sur Next.

Windows Deployment Services Image Capture Wizard X	
New Image Location	
Enter a local location where you want to save the install image. This ensures the image is not corrupted if there is a network malfunction. Name and location: Browse D:\Umage\CapturedImage.wim Browse Image \CapturedImage to a Windows Deployment Services server (optional) Server name: SRV2012R2-Depl2 Connect Image Group name: Windows 7 SP1 x64 To create this image, click Next. To	
< Back Next > Cancel	

19. La prochaine fenêtre vous affichera l'état d'avancement de la capture du poste. Une fois terminée, cliquez sur **Finish.**

Vindows Deployment Services Image Capture Wizard	
Task Progress Capturing image	
Percent complete: 0%	
	×r.
<back cancel<="" finish="" td=""><td></td></back>	

Création d'un serveur DFS (Distributed File System)

Le service DFS de Microsoft est une technologie implantée dans toutes les versions de Windows Server depuis la version Windows 2000 et fut initialement introduit dans NT 4.0. DFS est un ensemble de services côté client et côté serveur qui permet de regrouper en un système de fichiers distribué (DFS) plusieurs partages réseau de type SMB. Le système DFS permet d'avoir une transparence au niveau de la location réelle du partage et permet une redondance sur le réseau en permettant aux partages d'être regroupés logiquement dans un seul dossier DFS.

Une racine DFS peut seulement exister sur une version serveur de Windows (NT 4.0 et supérieur) ou OpenSolaris ainsi qu'un ordinateur ayant le serveur Samba. Dans les versions Enterprise et Data Center de Windows Server, le système d'exploitation peut être l'hôte de plusieurs racines DFS.

Il existe deux types d'implémentation du DFS :

- Standalone DFS namespaces : N'utilise pas Active Directory. La racine DFS est située sur l'ordinateur local. Il ne peut être relié à aucun autre DFS sur le réseau. Il n'offre aucune tolérance de faute. Un serveur DFS standalone est rarement implémenté vu ses capacités limitées.
- Domain-based DFS namespaces : Stock la configuration DFS au sein même d'Active Directory. La racine DFS est accessible à l'URL \domainName\dfsRoot. La racine n'a pas besoin d'être configurée sur le contrôleur de domaine ; elle peut être sur des serveurs membres du domaine. Une solution comportant plusieurs serveurs sur le domaine devrait être utilisée pour offrir une tolérance de panne des partages réseau.

Dans notre cas, nous n'avions pas de contrôleur de domaine sur le réseau. C'est pourquoi nous avons installé un serveur DFS en mode *standalone*. Il aurait toutefois été très intéressant d'explorer la solution *domain-based* puisque c'est celle-ci que nous retrouvons le plus souvent en entreprise. Toutefois, cela ne faisait pas partie du cours.

Le service est relativement léger dans son opération au niveau mémoire vive et processeur, de même qu'au niveau de l'espace disque. Au niveau des composants réseau, le serveur se doit d'être câblé sur un réseau Gigabit pour délivrer des performances acceptables.

Voici la configuration de la machine virtuelle SRV2012R2-DFS :

Paramètre	Réglage
Hardware Compatibility	Workstation/ESXi 10.0
CPU	4 Cores, no HT
RAM	2 GB
HDD	60 GB, LSI Logic SAS, SCSI
Network Adapter	Bridged, connected directly to physical network. Connected at power on.
Virtualized Operating System	Microsoft Windows Server 2012 R2 Update 1

À des fins de tests, nous avons utilisé, en plus du serveur SRV2012R2-DFS, deux autres serveurs ayant pour rôle un serveur de fichiers Samba, soit SRV2012R2-SMB1 et SRV2012R2-SMB2. Voici la configuration de ces deux machines virtuelles :

Paramètre	Réglage
Hardware Compatibility	Workstation/ESXi 10.0
CPU	4 Cores, no HT
RAM	2 GB
HDD	40 GB, LSI Logic SAS, SCSI
Network Adapter	Bridged, connected directly to physical network. Connected at power on.
Virtualized Operating System	Microsoft Windows Server 2012 R2 Update 1

Partie 1 : Création des serveurs Samba

Sur chacun des deux serveurs Samba, nous avons partagé un dossier à la racine du disque dur virtuel. Sur SRV2012R2-SMB1, le dossier *C*:*Wetworking* fut partagé, alors que sur SRV2012R2-SMB2, le dossier *C*:*Programming* fut partagé.

1. Cliquez droit sur le dossier à partager, puis cliquez sur Properties,



2. Dans l'onglet Sharing, cliquez sur Advanced Sharing...



3. Cochez la case Share this folder. Entrez un nom de partage sous Share Name. Cliquez sur Permissions.

Advanced Sharing
✓ <u>S</u> hare this folder
Settings
S <u>h</u> are name:
Programming
Add Remove
Limit the number of simultaneous users to:
Comments:
Permissions Caching
OK Cancel Apply

4. **Paratagez** le dossier avec le groupe **Everyone**. Accorder le contrôle total au groupe en cochant la case **Allow Full Control**. Cliquez sur **Apply** puis sur **OK**, et **répétez** ces deux clics dans la **fenêtre Advanced Sharing**.

Permissions for	or Programmir	ng	x
Share Permissions			
Group or user names:			
& Everyone			
			_
	A <u>d</u> d	<u>R</u> emove	
Permissions for Everyone	Allow	Deny	
Full Control			
Change	✓		
Read	\checkmark		
	Canaal	And	
UK	Cancel	Apply	

5. Le résultat du partage devrait être comme suit :

R	Р	rogram	ming Propertie	es 🗙	:
General	Sharing	Security	Previous Versions	Customize	
Netwo	ork File and	Folder Sh	aring		
	Progra Shared	mming 1			
<u>N</u> etw \\SR	ork Path: V2012R2-S	6MB2\Prog	gramming		
<u>s</u>	hare				
Advar	nced Sharir	ng			
Set c advar	ustom perm nced sharir	nissions, cr ng options.	eate multiple shares,	and set other	
	A <u>d</u> vanced	d Sharing			
Passv	vord Protec	tion			
People must have a user account and password for this computer to access shared folders.					
To change this setting, use the <u>Network and Sharing Center</u> .					
		Clo	ose Cance	I <u>A</u> pply	

6. **Répétez l'opération** sur le serveur SRV2012R2-SMB2 pour créer un second dossier de partage.

Partie 2 : Configuration du serveur DFS

1. Installez le rôle DFS à partir du Server Manager. Le rôle se situe sous File and Storage Services, File and iSCSI Services, DFS Namespaces. Cochez la case.

a	Add Roles and Features Wizard	_ D X
Before You Begin Installation Type Server Selection Server Roles Features Confirmation Results	Add Roles and Features Wizard Select one or more roles to install on the selected server. Roles DNS Server Fax Server File and Storage Services (2 of 12 installed) File and Storage Services (1 of 11 installed) File Server (Installed) File Server (Installed) File Server (Installed) File Server (Installed) DrS Replication DFS Replication File Server Resource Manager	DESTINATION SERVER SRV2012R2-DFS Description DFS Namespaces enables you to group shared folders located on different servers into one or more logically structured namespaces. Each namespace appears to users as a single shared folder with a series of subfolders. However, the underlying structure of the namespace can consist of numerous shared folders located on different servers and in multiple sites.
	File Server VSS Agent Service iSCSI Target Server iSCSI Target Storage Provider (VDS and VSS) Server for NFS <	> <u>I</u> nstall Cancel

2. Confirmez en cliquant sur Add Features.



3. Cliquez sur Next.

à	Add Roles and Features Wizard	_ D X
Before You Begin Installation Type Server Selection Server Roles Features	Add Roles and Features Wizard Select one or more roles to install on the selected server. Roles DNS Server Fax Server Fine and Storage Services (2 of 12 installed)	DESTINATION SERVER SRV2012R2-DFS Description DFS Namespaces enables you to group shared folders located on different servers into one or more logically structured namespaces.
Confirmation Results	▲ ■ File and iSCSI Services (1 of 11 installed) ● File Server (Installed) ● BranchCache for Network Files ● Data Deduplication ● DFS Namespaces ● DFS Replication ● File Server Resource Manager ● File Server VSS Agent Service ● iSCSI Target Server ● iSCSI Target Storage Provider (VDS and VSS) ● Server for NFS	Each namespace appears to users as a single shared folder with a series of subfolders. However, the underlying structure of the namespace can consist of numerous shared folders located on different servers and in multiple sites.
	< <u>P</u> revious <u>Next</u>	> Install Cancel

4. Dans la fenêtre des **Features**, cliquez sur **Next.**

A	Add Roles and Features Wizard	
Select features		DESTINATION SERVER SRV2012R2-DFS
Before You Begin	Select one or more features to install on the selected server.	
Installation Type	Features	Description
Server Selection	NFT Framework 3.5 Features	.NET Framework 3.5 combines the
Server Roles	 NET Framework 4.5 Features (2 of 7 installed) 	power of the .NET Framework 2.0 APIs with new technologies for
Features	▷ Background Intelligent Transfer Service (BITS)	building applications that offer
Confirmation	BitLocker Drive Encryption	appealing user interfaces, protect
Results	BitLocker Network Unlock	information, enable seamless and
	BranchCache	secure communication, and provide
	Client for NFS	the ability to model a range of
	Data Center Bridging	business processes.
	Direct Play	
	Enhanced Storage	
	Failover Clustering	
	Group Policy Management	
	IIS Hostable Web Core	
	Ink and Handwriting Services	
	< Previous Next >	Install Cancel

5. Dans la fenêtre Confirmation, cochez la case Restart the destination server automatically if required puis cliquez sur Install.

B	Add Roles and Features Wizard	_ D X
Confirm installati	ion selections	DESTINATION SERVER SRV2012R2-DFS
Before You Begin	To install the following roles, role services, or features on selected server, click	k Install.
Installation Type	Restart the destination server automatically if required	
Server Selection Server Roles	Optional features (such as administration tools) might be displayed on this p been selected automatically. If you do not want to install these optional feature their check boxes.	age because they have Ires, click Previous to clear
Features		
Confirmation Results	File and Storage Services File and iSCSI Services DFS Namespaces Remote Server Administration Tools Role Administration Tools File Services Tools DFS Management Tools	
	Export configuration settings Specify an alternate source path	
	< <u>P</u> revious <u>N</u> ext >	Install Cancel

6. Le rôle DFS s'installera.

	Add Roles and Features Wizard
Installation progr	CSS DESTINATION SERVER SRV2012R2-DFS
Before You Begin	View installation progress
Installation Type	i Feature installation
Server Roles	Installation started on SRV2012R2-DFS
Features Confirmation Results	File and Storage Services File and iSCSI Services DFS Namespaces Remote Server Administration Tools Role Administration Tools File Services Tools DFS Management Tools
	You can close this wizard without interrupting running tasks. View task progress or open this page again by clicking Notifications in the command bar, and then Task Details. Export configuration settings
	< <u>P</u> revious <u>N</u> ext > Close Cancel

7. Lorsque le rôle est installé, cliquez sur Close.

Ē.	Add Roles and Features Wizard	_ 🗆 🗙
Installation progre	5S	DESTINATION SERVER SRV2012R2-DFS
Before You Begin	View installation progress	
Installation Type	Feature installation	
Server Selection		
Server Roles	Installation succeeded on SRV2012R2-DFS.	
Features	File and Storage Services	
Confirmation	File and iSCSI Services	
Results	DFS Namespaces	
	Remote Server Administration Tools Role Administration Tools	
	File Services Tools	
	DFS Management Tools	
	You can close this wizard without interrupting running tasks. View task p page again by clicking Notifications in the command bar, and then Task	rogress or open this Details.
	Export configuration settings	
	< <u>P</u> revious <u>N</u> ext >	Cancel

8. Dans le Server Manager, dans le rôle File and Storage, **cliquez droit sur le serveur local**, puis cliquez sur **DFS Management**.

b			Server Manager				J X
\mathbf{E}	● ✓ ✓ File and	Storage Servi	ices • Servers	• © 🖡	Manage Tools	View	Help
III III IIII IIII	Servers Volumes Disks Storage Pools Shares iSCSI Work Folders	SERVERS All servers 1 tot Filter Server Name IPv4 SRV2012R2-DFS 10.0 C EVENTS All events 1 total Filter Server Name ID SRV2012R2-DFS 46	Address Manageability DFS Management Add Roles and Features Shut Down Local Server Computer Management Remote Desktop Connection Windows PowerShell Configure Windows Automatic Feedback Manage As Start Performance Counters Refresh Copy Severity Source Log Date and Time Error volmgr System 5/3/2014 4:50:51 PM	Last Update 5/4/2014 10:45:01 AM	Windows Activation 00253-50000-00000-A	TASKS	▲
					• 🖻	2 🕼	0:45 AM 5/4/2014

9. Dans la console **DFS Management, cliquez droit sur Namespaces**, puis cliquez sur **New Namespaces...** pour créer un nouvel espace DFS.



10. Entrez le nom du serveur qui sera l'hôte DFS. Cliquez ensuite sur Next.

6	New Namespace Wizard	_ 🗆 X
Namespace Se	erver	
Steps: Namespace Server	Enter the name of the server that will host the namespace. The server you specify will be known as the namespace server.	
Namespace Name and Settings Namespace Type	Server: SRV2012R2-DFS Browse	
Review Settings and Create Namespace		
Confirmation		
	< Previous Next >	Cancel

11. Entrez le nom de l'espace DFS (DFS Namespace). En l'occurrence, nous avons choisi *Electronics*. Cliquez par la suite sur Edit Settings.

<u>^</u>	New Namespace Wizard	
Namespace N	ame and Settings	
Steps: Namespace Server	Enter a name for the namespace. This name will appear after the server or domain name in the namespace path, such as \\Server\Name or \\Domain\Name.	
Namespace Name and Settings	Name:	
Namespace Type	Electronics	
Review Settings and Create Namespace	Example: Public	
Confirmation	If necessary, the wizard will create a shared folder on the namespace server. To modify the settings of the shared folder, such as its local path and permissions, click Edit Settings. Edit Settings	
	< <u>P</u> revious <u>N</u> ext > Cancel	

12. Cochez la case Administrators have full access; other users have read and write permissions. Cliquez ensuite sur OK puis sur Next sur la fenêtre Namespace Name and Settings.

Edit Settings	x
Namespace server:	
SRV2012R2-DFS	
Shared folder:	
Electronics	
Local path of shared folder:	_
C:\DFSRoots\Electronics Browse	
Shared folder p <u>e</u> rmissions:	-
 All users have read and write permissions 	
 Administrators have full access; other users have read-only permissions 	
 Administrators have full access; other users have read and write permissions 	
O Use custom permissions: Customize	
OK Cancel	

13. Puisque nous ne sommes pas dans un environnement *Active Directory,* **cochez** la case **Stand-alone namespace. Cliquez** ensuite sur **Next**.

4	New Namespace Wizard						
Namespace Type							
Steps: Namespace Server Namespace Name and Settings Namespace Type Review Settings and Create Namespace Confirmation	Select the type of namespace to create. <u>Domain-based namespace</u> A domain-based namespace is stored on one or more namespace servers and in Active Directory Domain Services. You can increase the availability of a domain-based namespace by using multiple servers. When created in Windows Server 2008 mode, the namespace supports increased scalability and access-based enumeration.						
	\\SRV2012R2-DFS\Electronics < Previous Next > Cancel						

14. Cliquez sur **Create** après avoir révisé les paramètres de l'espace DFS.

*	New Namespace Wizard					
Review Settings and Create Namespace						
Steps: Namespace Server Namespace Name and Settings Namespace Type Review Settings and Create Namespace Confimation	You selected the following settings for the new namespace. If the settings are correct, click Create to create your new namespace. To change a setting, click Previous, or select the appropriate page in the orientation pane. Namespace gettings: Namespace Namespace name: \\SRV2012R2-DFS\Electronics Namespace type: Stand-alone Namespace server: SPV2012R2-DFS Root shared folder: A shared folder will be created if one does not exist. Local path of namespace shared folder: C\DFSRoots\Electronics Permissions for namespace shared folder: Administrator full control, everyone read/write					
	< <u>P</u> revious Create Cancel					

15. L'espace DFS fut créé lorsque la fenêtre Confirmation apparaîtra.

4	New Namespace Wizar	d	_ D X
Confirmation			
Steps:			
Namespace Server	You have successfully completed the New N	lamespace Wizard.	
Namespace Name and Settings	Tasks Errors		
Namespace Type	Task	Status	
Review Settings and Create Namespace	🔇 Create namespace.	Success	
Confirmation			
			Close

16. Cliquez droit sur la nouvelle DFS namespace Electronics et cliquez sur Properties.

6		DFS Management	_ 0 ×	
🐴 File Action Vi	ew Window Help		_ <i>8</i> ×	
🗢 🄿 🙎 📰 🗉				
Carl Contract Contrac	Namespaces	A	ctions	
A A Namespaces	Name	N	lamespaces 🔺	
Replication	New Folder		💈 New Namespace	
	Delegate Management Permissions		🗯 Add Namespaces to Di	
	Remove Namespace from Display		Delegate Management	
	New Window from Here		View 🕨	
	Delete		New Window from Here	
	Refresh		Export List	
	Properties		Help	
	Help			
< III				
Upens the properties dialog box for the current selection.				
			 10:59 AM 5/4/2014 	
17. Dans l'onglet **Advanced**, assurez-vous que la case **Enable access-based enumeration for this namespace** est cochée. Cliquez sur **Apply** puis sur **OK**.

\\srv2012r2-dfs\electronics Properties
General Referrals Advanced
Access-based enumeration hides folders in this namespace that users do not have permission to view.
Enable access-based enumeration for this namespace
OK Cancel Apply

18. Cliquez droit sur l'espace *Electronics*, puis sur New Folder...



19. Entrez un nom de dossier. Cliquez sur Add... puis entrez le chemin vers le dossier qui se trouve sur un serveur Samba distant, en l'occurrence SRV2012R2-SMB1.

🐴	DFS Management	
Image: Dest Management ▲ Landstand ▲ Landstand ▲ Landstand ▲ Replication	VSRV2012R2-DFS\Electronics (Stand-alone namespace)	Actions \\SRV2012R2-DFS\Ele ▲ Image: State of the state of
🕂 占 🛛 🚞	G	▲ 🕲 👍 11:42 AM

20. La fenêtre New Folder devrait être semblable à celle ci-dessous. Cliquez sur OK.

	New Folder	x
<u>N</u> ame:		
Networking		
Preview of name	space:	
\\SRV2012R2-D	FS\Electronics\Networking	
Folder targets:		
\\SRV2012R2-S	MB1\Networking	
<u>A</u> dd	Edit <u>R</u> emove	
	Cano	,ei

21. Le nouveau dossier devrait se retrouver dans la console DFS Management.

~	DFS Management	_ 0 ×
Eile Action View Window Help		_ 8 ×
🗢 🌩 🖄 🖬 👔		
Contract Con	\\SRV2012R2-DFS\Electronics (Stand-alone namespace)	Actions
⊿ № Namespaces N № \\SRV2012R2-DES\Electronics	Namespace Namespace Servers Delegation Search	\\SRV2012R2-DFS\Ele
Replication	1 entries	🕂 New Folder
	Type Name /	Delegate Management
	Retworking	Remove Namespace fr
		View 🕨
		New Window from Here
		🗙 Delete
		a Refresh
		Properties
		? Help
		9

22. Testez la configuration. Faites les touches **WINDOWS+R** pour ouvrir une fenêtre d'exécution, puis tapez le chemin du serveur DFS : \\SRV2012R2-DFS\Electronics.

Recycle Bin			
2 			
	Run		
Open:	Iype the name of a program, folder, document, or internet resource, and Windows will open it for you. INSRV2012R2-DFS\Electronics Instask will be created with administrative privileges.		
	OK Cancel <u>B</u> rowse	▲ P ² @ € 11:51/ 5/4/2	AM 014

23. Après avoir entré un nom d'utilisateur (administrateur ou autre, puisque les dossiers sont ouverts à tous les utilisateurs), vous obtiendrez la liste des dossiers partagés. Le dossier *Networking* est situé sur le serveur SRV2012R2-SMB1, alors que le dossier *Programming* est situé sur le serveur SRV2012R2-SMB2.



Création d'un serveur LAMP

La fondation Apache (ou *Apache Foundation Software*) est une organisation à but non lucratif qui fournit plus de 140 projets logiciels OpenSource. La fondation procure ainsi les bases pour étendre les propriétés intellectuelles de plusieurs domaines différents. C'est par un processus de collaboration unique nommé *The Apache Way* que la fondation Apache met à la disposition de nombre de communautés d'utilisateurs des produits de classe entreprise tout à fait gratuitement. La licence Apache permet l'implantation de produits Apache autant dans des milieux commerciaux qu'à usage personnel.

Dans le cadre de ce projet, ce fut le serveur Apache HTTP qui fut choisi d'implanté au sein du système. Conçu dans la mentalité d'Apache, le serveur HTTP de la fondation est robuste, fiable et totalement OpenSource. C'est par conséquent une plateforme de serveur développée par des volontaires de partout dans le monde qui utilise la puissance du Web pour communiquer afin de perfectionner cette plateforme.

Le serveur Apache HTTP est conçu pour être opéré sur des plateformes UNIX, UNIX-*Like* et Windows NT. Le but de ce serveur être d'être sécuritaire, accessible, efficace et peu coûteux à mettre en place. Vu ses qualités, c'est plus de 100 millions de sites web dans le monde qui utilisent cette plateforme pour livrer leurs services et leurs informations. Apache fut le premier serveur à franchir cet important cap.

Le serveur Apache ne fonctionne pas seul. Aujourd'hui, plusieurs sites web se doivent d'avoir une base de données pour stocker diverses informations. Le composant MySQL est un système de gestion de bases de données et il fait partie des logiciels de bases de données les plus utilisés dans le monde. MySQL opère avec le langage Structured Query Language. MySQL est multi-threaded et multi-utilisateur et intègre des composants de sécurité. MySQL est disponible sous une multitude de systèmes d'exploitation : AIX, IBM i-5, BSDi, FreeBSD, HP-UX, Linux, Mac OS X, NetWare, NetBSD, OpenBSD, OS/2 Warp, SGI IRIX, Solaris, SCO OpenServer, SCO UnixWare, Tru64 Unix et Windows. Les bases de données sont accessibles en utilisant les langages de programmation C, C++, VB, VB .NET, C#, Delphi/Kylix, Eiffel, Java, Perl, PHP, Python, Windev, Ruby et Tcl.

De plus en plus de sites web utilisent également le langage de programmation PHP. Puisque le PHP est un langage interprété côté serveur, on se doit aujourd'hui d'intégrer un interpréteur PHP au sein du service web Apache. La solution complète porte donc l'acronyme LAMP, pour *Linux, Apache, MySQL and PHP*.

Samba est quant à lui un logiciel d'interopérabilité qui permet à des ordinateurs UNIX de mettre à disposition des imprimantes et des fichiers dans des réseaux Windows, en mettant en œuvre le protocole SMB/CIFS de Microsoft Windows. Samba peut également faire parti d'un

Active Directory. Samba opère dans la vaste majorité des systèmes d'exploitation UNIX et UNIX-Like tels que Mac OS X, Linux, Solaris et BSD. Samba est un standard dans pratiquement toutes les grandes distributions Linux, que ce soit dans les branches Debian, Slackware Linux ou Red Hat. Il fonctionne sur le principe de client/serveur. Un serveur Samba permet de partager des disques ou des ressources pour que d'autres machines puissent accéder à ces ressources. À l'inverse, un client peut également se retrouver serveur d'une autre machine alors que cette dernière demande accès à ses ressources.

Dans le cas ci-présent, un serveur de partage Samba est configuré pour que toutes les autres machines ou des appareils mobiles du réseau puissent avoir accès aux fichiers partagés. Le tout est configuré dans le serveur Samba de CentOS.

Le serveur Apache fut installé sur le système d'exploitation CentOS 6.5. L'installation se déroule entièrement en ligne de commandes. Le « **#** » signifie que la ligne de commande doit être effectuée en tant qu'utilisateur *root*. La syntaxe du langage *Bash (Shell)* fut gardée tout au long de cette partie du document.

Paramètre	Réglage
Hardware Compatibility	Workstation/ESXi 10.0
CPU	2 Cores, no HT
RAM	1.5 GB
HDD	40 GB, LSI Logic SAS, SCSI
Network Adapter	Bridged, connected directly to physical network. Connected at power on.
Virtualized Operating System	Community ENTerprise Operating System (CentOS) 6.5 Linux Kernel 2.6.32

Voici la configuration matérielle de la machine CentOS-Web-6.5

Partie 1 : Installation de MySQL

1. Il se peut que vous ayez besoin du répertoire EPEL. EPEL est un répertoire d'applications pour Fedora. Il vous faudra donc **ajouter le répertoire EPEL** de Fedora à CentOS.

```
# COMMANDE
```

- 1 # wget <u>http://download.fedoraproject.org/pub/epel/6/x86_64/</u> epel-release-6-8.noarch.rpm
- 2 # sudo rpm -ivh epel-release*
- 2. Installez MySQL
- # COMMANDE
- 1 # yum install mysql mysql-server
- 3. Activer et démarrer le service MySQL.
- # COMMANDE
- 1 # /sbin/chkconfig --add mysqld
- 2 **# service** mysqld start
- 4. Démarrez l'installation de MySQL.

COMMANDE

1 # mysql_secure_installation

5. Suivez le déroulement suivant :

TEXTE 1 NOTE: RUNNING ALL PARTS OF THIS SCRIPT IS RECOMMENDED FOR ALL MySQL 2 SERVERS IN PRODUCTION USE! PLEASE READ EACH STEP CAREFULLY! 3 In order to log into MySQL to secure it, we'll need the current 4 password for the root user. If you've just installed MySQL, and

#	TEXTE
5	you haven't set the root password yet, the password will be blank,
6	so you should just press enter here.
7	Enter current password for root (enter for none): < ENTER
8	OK, successfully used password, moving on
9	Setting the root password ensures that nobody can log into the MySQL
10	root user without the proper authorisation.
11	Set root password? [Y/n] < ENTER
12	New password: < entrez le mot de passe SQL pour l'utilisateur root.
13	Re-enter new password: < confirmez le mot de passe
14	Password updated successfully!
15	Reloading privilege tables
16	Success!
17	By default, a MySQL installation has an anonymous user, allowing
17 18	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account
17 18 19	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing
17 18 19 20	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove
17 18 19 20 21	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment.
17 18 19 20 21	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment.
 17 18 19 20 21 22 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER
 17 18 19 20 21 22 23 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success!
 17 18 19 20 21 22 23 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success!
 17 18 19 20 21 22 23 24 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success! Normally, root should only be allowed to connect from 'localhost'.
 17 18 19 20 21 21 22 23 24 25 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success! Normally, root should only be allowed to connect from 'localhost'. This ensures that someone cannot guess at the root password from
 17 18 19 20 21 21 22 23 24 25 26 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success! Normally, root should only be allowed to connect from 'localhost'. This ensures that someone cannot guess at the root password from the network.
 17 18 19 20 21 21 22 23 24 25 26 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success! Normally, root should only be allowed to connect from 'localhost'. This ensures that someone cannot guess at the root password from the network.
 17 18 19 20 21 22 23 24 25 26 27 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success! Normally, root should only be allowed to connect from 'localhost'. This ensures that someone cannot guess at the root password from the network. Disallow root login remotely? [Y/n] < n , suivit de ENTER
 17 18 19 20 21 22 23 24 25 26 27 28 	By default, a MySQL installation has an anonymous user, allowing anyone to log into MySQL without having to have a user account created for them. This is intended only for testing, and testing and to make the installation go a bit smoother. You should remove them before moving into a production environment. Remove anonymous users? [Y/n] < ENTER Success! Normally, root should only be allowed to connect from 'localhost'. This ensures that someone cannot guess at the root password from the network. Disallow root login remotely? [Y/n] < n , suivit de ENTER Success!

#	ТЕХТЕ
29	By default, MySQL comes with a database named 'test' that anyone can
30	access. This is also intended only for testing, and should be removed
31	before moving into a production environment.
32	Remove test database and access to it? [Y/n] < ENTER
33	- Dropping test database
34	Success!
35	 Removing privileges on test database
36	Success!
37	
38	Reloading the privilege tables will ensure that all changes made so far
39	will take effect immediately.
40	
41	Reload privilege tables now? [Y/n] < ENTER
42	Success!
43	
44	Reload privilege tables now? [Y/n] < ENTER
45	Success!
46	
47	Cleaning up
48	
49	All done! If you've completed all of the above steps, your MySQL
50	installation should now be secure.
51	Thanks for using MySQL!

Partie 2 : Activation du pare-feu

1. Activer le pare-feu pour laisser passer les connexions Samba. Si vous n'avez pas d'environnement graphique sur votre serveur, saisissez la commande suivante :

COMMANDE

1 # system-config-firewall-tui

Cette commande affichera une simili-interface graphique pour le pare-feu. Cliquez sur Customize en positionnant le curseur sur la case et en appuyant sur ENTER.



Sélectionnez le service WWW (HTTP) en appuyant sur **SPACE** sur le service. Par la suite, positionnez le curseur sur **Close.**



Appuyez sur OK.



Appuyez sur Yes.



Si vous disposez d'un **environnement graphique**, saisissez la commande suivante :

#	COMMANDE
1	<pre># system-config-firewall</pre>

La fenêtre de configuration du pare-feu s'affichera. Après avoir **rentré le mot de passe root**, **cochez la case WWW (HTTP)** puis cliquez sur **Apply.**

- -	Firewall Configurat	ion	_ = ×
<u>F</u> ile <u>O</u> ptions <u>H</u> elp			
Wizard Apply Reloa	ad Enable Disable		
Trusted Services H Other Ports a	lere you can define which services a Il hosts and networks.	re trusted. Trusted servic	es are accessible from
Trusted Interfaces	Service	✓ Port/Protocol	Conntrack Helper
Masquerading Port Forwarding	Red Hat Cluster Suite	11111/tcp, 21064/tcp, 5404/udp, 5405/udp	
ICMP Filter Custom Rules	✓ Samba	139/tcp, 445/tcp, 137/ udp, 138/udp	netbios_ns
8	 Samba Client 	137/udp, 138/udp	netbios_ns
	Secure WWW (HTTPS)	443/tcp	
	✓ SSH	22/tcp	
	TFTP	69/udp	tftp
	TFTP Client		tftp
	Virtual Machine Management	16509/tcp	
	Virtual Machine Management (TL	S) 16514/tcp	
	WWW (HTTP)	80/tcp	
4	Allow access to necessary servic	es, only.	
The firewall is enabled. (n	nodified)		

Partie 3 : Installation de Apache HTTP Server

1. Installez Apache HTTP Server

COMMANDE

- 1 **# yum install** httpd
- 2. Activez et démarrez le service httpd.

COMMANDE

- 1 # /sbin/chkconfig --add https
- 2 # service https start

Le serveur Apache HTTP est maintenant fonctionnel. Il suffit d'entrer l'adresse IP du serveur pour constater son fonctionnement. Vous pourrez visionner en annexe le fichier de configuration de notre serveur. Le fichier de configuration se trouve dans le répertoire suivant :

RÉPERTOIRE

1 /etc/httpd/conf/httpd.conf

8 C 10.0.3.248 - Apache HTTP Server Test Page powered by CentOS	C Reader
Apache 2 powered by	Test Page CentOS
This page is used to test the proper operation of the Apache HTTP server after it has been installed. If yo	ou can read this page it means that the Apache HTTP server installed at this site is working properly.
If you are a member of the general public:	If you are the website administrator:
The fact that you are seeing this page indicates that the website you just visited is either experiencing problems or is undergoing routine maintenance.	You may now add content to the directory /var/www/html/. Note that until you do so, people visiting your website will see this page and not your content. To prevent this page from ever being used (follow the instructions in the file (for the follow for a follow for a formation of the formation of the follow).
If you would like to let the administrators of this website know that you've seen this page instead of the page you expected, you should send them e-mail. In general, mail sent to the name "webmaster" and directed to the website's domain should reach the appropriate person.	used, follow the mean declarate in the line year of the part of the declarate count of the declarate count. You are free to use the images below on Apache and CentOS Linux powered HTTP servers. Thanks for using Apache and CentOS!
For example, if you experienced problems while visiting www.example.com, you should send e- mail to "webmaster@example.com".	
About CentOS:	
The Community ENTerprise Operating System (CentOS) is an Enterprise-class Linux Distribution der CentOS conforms fully with the upstream vendors redistribution policy and aims to be 100% binary comp CentOS Project is the organization that builds CentOS.	ived from sources freely provided to the public by a prominent North American Enterprise Linux vendor. atlible. (CentOS mainly changes packages to remove upstream vendor branding and artwork.) The
For information on CentOS please visit the CentOS website.	
Note:	
CentOS is an Operating System and it is used to power this website; however, the webserver is owned b contact the owner of the domain, not the CentOS project.	by the domain owner and not the CentOS Project. If you have issues with the content of this site,
Unless this server is on the CentOS.org domain, the CentOS Project doesn't have anything to do with th	e content on this webserver or any e-mails that directed you to this site.

For example, if this website is www.example.com, you would find the owner of the example.com domain at the following WHOIS server:

http://www.internic.net/whois.html

Partie 4 : Installation d'un module PHP

1. Installez PHP ainsi que ses modules complémentaires.

APC est un *opcode cacher* gratuit et libre qui sert à mettre en cache et à optimiser le code intermédiaire de PHP. Pour de meilleures performances, il est recommandé d'installer ce module additionnel. Pour ce faire, il suffit de faire la ligne de commande ci-dessous :

COMMANDE

- 1 **# yum install** php
- 2 # yum install php-mysql php-gd php-imap php-ldap php-odbc php-pear php-xml php-xmlrpc php-magickwand php-mbstring phpmcrypt php-mssql php-shout php-snmp php-soap php-tidy
- 3 # yum install php-pecl-apc
- 2. Redémarrez le service Apache HTTP.

COMMANDE

1 # service httpd restart

Le répertoire racine pour le site web par défaut est /var/www/html. Nous allons créer un fichier php (info.php) dans ce répertoire et faire charger ce fichier dans le navigateur web. Ce fichier fera apparaître des renseignements importants et utiles à propos de l'installation de PHP.

Pour ce faire, toujours dans le Terminal en mode *power user*, effectuez la commande suivante :

COMMANDE

1 # nano /var/www/html/info.php

Cela créera un fichier vierge du non de info.php dans le répertoire.

Dans ce fichier, écrire les lignes de code suivantes :

#	COMMANDE
1	php</th
2	<pre>phpinfo();</pre>
3	?>

Faites CTRL+X pour sortir de l'éditeur de texte Nano et sauvegarder le fichier info.php.

Appeler le lien http://[ip address] : [port]/info.php dans le navigateur web. Une page web illustrant toutes les informations relatives à l'interpréteur PHP s'affichera.



Partie 5 : Installation de PHPMyAdmin

Une fois que PHP est installé, il faut par la suite installer le support MySQL dans PHP5.

1. Téléchargez et installez des supports additionnels MySQL pour PHP.

COMMANDE

- 1 **# yum install** phpmyadmin
- 2. Il faut désormais configurer PHPMyAdmin. Pour ce faire, il faut changer la configuration d'Apache pour faire en sorte que PHPMyAdmin n'accepte pas seulement les connexions de localhost.

COMMANDE

1 # nano /etc/httpd/conf.d/phpMyAdmin.conf

Le fichier de configuration devrait ressembler à celui ci-dessous :

#	ТЕХТЕ
1	# Allows only localhost by default
2	#
3	# But allowing phpMyAdmin to anyone other than localhost should be considered
4	<pre># dangerous unless properly secured by SSL</pre>
5	
6	Alias /phpMyAdmin /usr/share/phpMyAdmin
7	Alias /phpmyadmin /usr/share/phpMyAdmin
8	
9	<directory phpmyadmin="" share="" usr=""></directory>
10	<ifmodule mod_authz_core.c=""></ifmodule>
11	# Apache 2.4
12	<requireany></requireany>
13	Require ip 127.0.0.1
14	Require ip ::1
15	
16	
17	<ifmodule !mod_authz_core.c=""></ifmodule>

#	TEXTE
18	# Apache 2.2
19	Order Deny,Allow
20	# Deny from All
21	Allow from 127.0.0.1
22	Allow from ::1
23	
24	Require all granted
25	
26	
27	<directory phpmyadmin="" setup="" share="" usr=""></directory>
28	<lfmodule mod_authz_core.c=""></lfmodule>
29	# Apache 2.4
30	<requireany></requireany>
31	Require ip 127.0.0.1
32	Require ip ::1
33	
34	
35	<lfmodule !mod_authz_core.c=""></lfmodule>
36	# Apache 2.2
37	Order Deny,Allow
38	Deny from All
39	Allow from 127.0.0.1
40	Allow from ::1
41	
42	
43	
44	# These directories do not require access over HTTP - taken from the original
45	<pre># phpMyAdmin upstream tarball</pre>
46	#
47	<directory libraries="" phpmyadmin="" share="" usr=""></directory>
48	Order Deny,Allow

#	ТЕХТЕ
49	Deny from All
50	Allow from None
51	
52	
53	<directory lib="" phpmyadmin="" setup="" share="" usr=""></directory>
54	Order Deny,Allow
55	Deny from All
56	Allow from None
57	
58	
59	<directory frames="" phpmyadmin="" setup="" share="" usr=""></directory>
60	Order Deny,Allow
61	Deny from All
62	Allow from None
63	
64	
65	# This configuration prevents mod_security at phpMyAdmin directories from
66	# filtering SQL etc. This may break your mod_security implementation.
67	#
68	# <ifmodule mod_security.c=""></ifmodule>
69	# <directory phpmyadmin="" share="" usr=""></directory>
70	# SecRuleInheritance Off
71	#
72	#

3. Redémarrer le service Apache HTTP.

COMMANDE

1 # service httpd restart

4. Se connecter à l'interface PHPMyAdmin via un navigateur Web.

To rever this page, you must log in to this area on 10.0.3.248:80: phpMyAdmin localhost Your password will be sent unencrypted. Name: Password: Remember this password in my keychain Cancel Log In	
Image: Second	eader
phpMyAdmin	
G Databases G Databases G SQL G Status SQL G Status Superior	
(Recent tables) Image: Constraint of the constrain	
Change password Server: Localhost via UNIX socket Software: MySQL Software: wySQL Software: wySQL Software: wySQL Software: wySQL Software: wySQL	
mysql Protoci Version: 10	
Appearance Settings • Server charset: UTF-8 Unicode (utf8)	
Language : English Theme: nmahamme 1	
Font size: 82% Catabase client version: librayal - 5.1.73	
PHP extension: mysqli 🕢	
phpMyAdmin	
Version information: 3.5.8.2, latest stable version: 4.1.14	
Documentation Wild Official Homepage	
Contribute Get support	
• List of changes	
A newer version of phpMyAdmin is available and you should consider upgrading. The newest version is 4.1.14, released on 2014-04-26.	
	

Si après la fin de l'installation les fichiers que contient le répertoire /var/www/html ne sont plus accessible sur le serveur, il faut modifier le fichier httpd.conf du répertoire /etc/httpd/conf et ajouter les lignes suivantes :

#	TEXTE
1	<directory></directory>
2	AllowOverride None
3	Order Deny,Allow
4	Deny from all
5	

# .	TEXTE
6 ·	<directory html="" var="" www=""></directory>
7	Order Deny,Allow
8	Allow from all
9	

Explication des lignes :

#	TEXTE
1	AllowOverride None

• Enlève l'accès aux utilisateurs de modifier le fichier .htaccess du serveur, ce qui permettrait de contourner des règles de sécurités pré-établies.

#	TEXTE
π	

- 1 Order Deny,Allow
- 2 Deny from all
 - Enlève le droit de visionner la racine du serveur (http://[IP address]:[Port]/), ce qui protège le système de fichier du serveur.

#	ТЕХТЕ
1	<directory html="" var="" www=""></directory>
2	Order Deny,Allow
3	Allow from all
4	

 Permets aux clients du serveur de consulter ce qu'il y a dans le contenu du répertoire /var/ www/html

Création d'un serveur Samba

Samba est quant à lui un logiciel d'interopérabilité qui permet à des ordinateurs UNIX de mettre à disposition des imprimantes et des fichiers dans des réseaux Windows, en mettant en œuvre le protocole SMB/CIFS de Microsoft Windows. Samba peut également faire partie d'un *Active Directory*. Samba opère dans la vaste majorité des systèmes d'exploitation UNIX et *UNIX-Like* tels que Mac OS X, Linux, Solaris et BSD. Samba est un standard dans pratiquement toutes les grandes distributions Linux, que ce soit dans les branches Debian, Slackware Linux ou Red Hat. Il fonctionne sur le principe de client/serveur. Un serveur Samba permet de partager des disques ou des ressources pour que d'autres machines puissent accéder à ces ressources. À l'inverse, un client peut également se retrouver serveur d'une autre machine alors que cette dernière demande accès à ses ressources.

Dans le cas ci-présent, un serveur de partage Samba est configuré pour que toutes les autres machines ou des appareils mobiles du réseau puissent avoir accès aux fichiers partagés. Le tout est configuré dans le serveur Samba de CentOS.

Le serveur Samba fut installé sur le système d'exploitation CentOS 6.5 dans la même machine virtuelle que le serveur LAMP. L'installation se déroule entièrement en ligne de commandes. Le « **#** » signifie que la ligne de commande doit être effectuée en tant qu'utilisateur *root*. La syntaxe du langage *Bash (Shell)* fut gardée tout au long de cette partie du document.

Partie 1 : Désactivation de SELinux

 Il faut d'abord s'assurer que le module SELinux (Security Enhanced Linux) soit désactivé. Sachez qu'on peut toutefois le laisser activer pour plus de sécurité, mais que la simple désactivation de ce module permet de rendre moins complexes l'installation et l'opération du serveur. Pour désactiver SELinux, il faut éditer le fichier *config* du répertoire /etc/selinux/config pour qu'il soit identique aux lignes décrites ci-dessous.

COMMANDE

1 # nano /etc/selinux/config

#	TEXTE
1	# This file controls the state of SELinux on the system.
2	<pre># SELINUX= can take one of these three values:</pre>
3	<pre># enforcing - SELinux security policy is enforced.</pre>
4	<pre># permissive - SELinux prints warnings instead of enforcing.</pre>
5	<pre># disabled - No SELinux policy is loaded.</pre>
6	SELINUX=disabled
7	<pre># SELINUXTYPE= can take one of these two values:</pre>
8	<pre># targeted - Targeted processes are protected,</pre>
9	<pre># minimum - Modification of targeted policy. Only selected</pre>
10	processes are protected
11	<pre># mls - Multi Level Security protection.</pre>
12	SELINUXTYPE=targeted

2. Il faut par la suite redémarrer le système pour que celui-ci applique la désactivation de SELinux.

COMMANDE

1 # reboot

Partie 2 : Installation du serveur Samba

1. Installez le serveur Samba.

COMMANDE

1 # yum install cups-libs samba samba-common samba-client

Pour configurer le serveur samba, il faut éditer le fichier smb.conf du répertoire /etc/samba. La configuration de base est satisfaisante pour les besoins de la machine ci-présente. Toutefois, pour des mesures de sécurité, il faut s'assurer d'avoir ces lignes écrites comme ci-dessous dans le fichier :

COMMANDE

1 # nano /etc/samba/smb.conf

```
# TEXTE
```

```
1 # ------ Standalone Server Options ------
2 # security = the mode Samba runs in. This can be set to user,
3 # share
4 # (deprecated), or server (deprecated).
5 #
6 # passdb backend = the backend used to store user information in.
7 # New installations should use either tdbsam or ldapsam. No
7 # additional configuration is required for tdbsam. The "smbpasswd"
8 # utility is available for backwards compatibility.
10 #
12 security = user
13 passdb backend = tdbsam
```

3. Activer le service Samba au démarrage et démarrer le service.

COMMANDE

- 1 # /sbin/chkconfig --add smb
- 2 # service smb start

Partie 3 : Activation du pare-feu

1. Activer le pare-feu pour laisser passer les connexions Samba. Si vous n'avez pas d'environnement graphique sur votre serveur, saisissez la commande suivante :

#	COMMANDE
1	<pre># system-config-firewall-tui</pre>

Cette commande affichera une simili-interface graphique pour le pare-feu. Cliquez sur Customize.



Cochez les cases Samba et Samba Client en appuyant sur la touche SPACE. Faites ensuite ENTER sur Forward.

Le reste de la configuration s'illustre comme suit :





Σ		root@centosweb:~	□ ×
File	Edit	View Search Terminal Help	
systen	n-con	ıfig-firewall	<u>^</u>
		Trusted Interfaces	
		Mark all interfaces as trusted which should have full access to the system.	
		[] isdn+ ↑ [] ppp+ ▓ [] tun+ ■ [] <mark>wlan+</mark> ↓	Ξ
		Forward Back Close	
<tal< td=""><td>b>/<a< td=""><td>llt-Tab> between elements <space> selects <f12> next scree</f12></space></td><td>n 🗸</td></a<></td></tal<>	b>/ <a< td=""><td>llt-Tab> between elements <space> selects <f12> next scree</f12></space></td><td>n 🗸</td></a<>	llt-Tab> between elements <space> selects <f12> next scree</f12></space>	n 🗸

	root@centosweb:~	_ (⊐ ×
File E	dit View Search Terminal Help		
system	-config-firewall		<u>^</u>
	Add entries to forward ports either from one port to another on the local system or from the local system to another system. Forwarding to another system is only useful if the interface is masqueraded. Port forwarding is IPv4 only.		III
<tab:< td=""><td>>/<alt-tab> between elements <space> selects <f12> next s</f12></space></alt-tab></td><td>cree</td><td>n 🗸</td></tab:<>	>/ <alt-tab> between elements <space> selects <f12> next s</f12></space></alt-tab>	cree	n 🗸



	root@centosweb:~	_ 🗆 🗙
File	Edit View Search Terminal Help	
syste	em-config-firewall	<u>_</u>
	Custom Rules	
	Use custom rules files to add additional rules to the firewall	
	The custom rules are added after the default rules. The files	
	must have the iptables-save format.	
	t	
		Ξ
	<add> <edit> <remove></remove></edit></add>	
	Back Close	
<ta< th=""><th>ab>/<alt-tab> between elements <space> selects <f12> next so</f12></space></alt-tab></th><th>:reen 🚽</th></ta<>	ab>/ <alt-tab> between elements <space> selects <f12> next so</f12></space></alt-tab>	:reen 🚽




Si vous disposez d'un **environnement graphique**, saisissez la commande suivante :

COMMANDE

1 # system-config-firewall

La fenêtre de configuration du pare-feu s'affichera. Après avoir **entré le mot de passe root**, **cochez les cases Samba** et **Samba Client** puis cliquez sur **Apply**.

.	Firewall Configurati	on	_ = ×
<u>F</u> ile <u>O</u> ptions <u>H</u> elp			
Wizard Apply Reloa	d Enable Disable		
Trusted Services H Other Ports a	ere you can define which services are Il hosts and networks.	e trusted. Trusted servic	es are accessible from
Trusted Interfaces	Service 🗸	Port/Protocol	Conntrack Helper
Masquerading Port Forwarding	Red Hat Cluster Suite	11111/tcp, 21064/tcp, 5404/udp, 5405/udp	
ICMP Filter Custom Rules	🛛 Samba	139/tcp, 445/tcp, 137/ udp, 138/udp	netbios_ns
6	Z Samba Client	137/udp, 138/udp	netbios_ns
	Secure WWW (HTTPS)	443/tcp	
8	SSH	22/tcp	
	TFTP	69/udp	tftp
	TFTP Client		tftp
	Virtual Machine Management	16509/tcp	
	Virtual Machine Management (TLS) 16514/tcp	
	WWW (HTTP)	80/tcp	
4	Allow access to necessary service	s, only.	
The firewall is enabled. (m	nodified)		

Partie 4 : Création d'un partage de fichiers

1. Pour partager des fichiers, créez un dossier de partage.

COMMANDE

- 1 # mkdir -p /samba/shares
- 2. Affectez ces dossiers des permissions UNIX 770.

COMMANDE

- 1 # chmod 770 /samba
- 2 # chmod 770 /samba/shares
- 3. Pour rendre le dossier accessible, ajoutez les lignes ci-dessous au fichier smb.conf :

COMMANDE

1 # nano /etc/samba/smb.conf

TEXTE

- 1 [allusers]
- 2 comment = All Users
- 3 path = /home/shares/allusers
- 4 valid users = @users
- 5 force group = users
- 6 create mask = 0660
- 7 directory mask = 0771
- 8 writable = yes
- 4. Pour ajouter des utilisateurs au partage Samba, il suffit d'effectuer la série de commandes suivantes :

COMMANDE

- 1 # useradd [utilisateur] -m -G users
- 2 # passwd [utilisateur]
- **3** # smbpasswd -a [utilisateur]
- 5. Si l'administrateur veut que les utilisateurs puissent écrire directement dans leur dossier /home, il faut enlever les caractères de commentaire sur les lignes suivantes et ajouter les deux dernières lignes.

#	ТЕХТЕ
1	[homes]
2	comment = Home Directories
3	browseable = no
4	valid users = %S
5	writable = yes
6	create mask = 0700
7	directory mask = 0700

6. Sauvegardez le fichier smb.conf.

7. **Testez** les **paramètres Samba** avec la commande ci-dessous et vérifiez si aucune erreur n'est détectée:

COMMANDE

1 # testparm

8. Redémarrez le service Samba et le service nmb.

COMMANDE

- 1 # service smb restart
- 2 # service nmb restart

Le serveur Samba est maintenant opérationnel. Sur un système d'exploitation Microsoft, vous pouvez y accéder de la même manière qu'un partage de fichiers entres machines Windows.

	Run ×
	Type the name of a program, folder, document, or Internet resource, and Windows will open it for you.
<u>O</u> pen:	\\10.0.3.248\shares V
	OK Cancel <u>B</u> rowse

Sur une machine Linux pourvu d'un environnement graphique, utilisez Nautilus.



Sur une machine Linux dépourvu d'environnement graphique, utilisez cette ligne de commandes :

COMMANDE

1 smbclient //<hostname>/<sharename> -U <username>

Pour monter (mount) le partage Samba, entrez la ligne suivante :

#	COMMAN	DE			
1	mount -t	smbfs -o	username= <username></username>	// <servername>/<sharename> /mnt/point/</sharename></servername>	

Sur Mac OS X, utilisez Finder.

Connect to Server
Server Address:
smb://10.0.3.248/shares + G •
Favorite Servers:
cifs://srvfich2/Depots
🕮 afp://10.0.2.2
🕮 cifs://srvfich2/Regulier/0966406
🕮 cifs://srvfich2/Publics
🕮 cifs://srvfich2/regulier/0966406
🕮 smb://10.0.3.3
🕮 ftps://pldelisle.no-ip.info
Remove Browse

Voici le résultat sur Windows :

👱 🕞 🕕 = I		shares			_ 🗆 🗙
File Home Share	View				~ 🕐
🔄 🏵 🕆 👖 🕨 Ne	etwork → 10.0.3.3 → shares		v ¢	Search shares	Q,
🔶 Favorites	Name	Date modified	Туре	Size	
Downloads	Welcome on Samba Server.txt	2014-05-04 11:08	Text Document	0 KB	
Desktop					
E Recent places					
🛤 This PC					
Desktop					
Documents					
🐌 Downloads					
🚺 Music					
📔 Pictures					
📔 Videos					
🃥 Local Disk (C:)					
🔊 RAID 1 Array Wester					
📷 RAID 1 Array Seagate					
👌 DVD Drive (F:) IRM_S					
👝 iSCSI LUN-1 (L:)					
📭 Network					
1 item					

Création d'un serveur FTP

« File Transfer Protocol » (protocole de transfert de fichiers), ou « FTP », est un protocole de communication destiné à l'échange informatique de fichiers sur un réseau TCP/IP. Il permet, depuis un ordinateur, de copier des fichiers vers un autre ordinateur du réseau, ou encore de supprimer ou de modifier des fichiers sur cet ordinateur. Ce mécanisme de copie est souvent utilisé pour alimenter un site web hébergé chez un tiers.

La variante de FTP protégée par les protocoles SSL ou TLS (SSL étant le prédécesseur de TLS) s'appelle FTPS. FTP sans cryptage est vulnérable et peu sécuritaire. Il ne devrait être utilisé que pour distribuer des données peu sensibles.

FTP obéit à un modèle client-serveur, c'est-à-dire qu'une des deux parties, le client, envoie des requêtes auxquelles réagit l'autre, appelé serveur. En pratique, le serveur est un ordinateur sur lequel fonctionne un logiciel lui-même appelé serveur FTP, qui rend publique une arborescence de fichiers similaire à un système de fichiers UNIX. Pour accéder à un serveur FTP, on utilise un logiciel client FTP (possédant une interface graphique ou en lignes de commandes).

FTP, qui appartient à la couche application du modèle OSI et du modèle ARPA, utilise une connexion TCP.

Par convention, deux ports sont attribués pour les connexions FTP : le port 21 pour les commandes et le port 20 pour les données. Pour le FTPS dit implicite, le port conventionnel est le 990.

Ce protocole peut fonctionner avec IPv4 et IPv6.

Par contrainte matérielle, ce serveur fut installé dans la même machine virtuelle que les services LAMP et Samba. Idéalement, nous aurions dû ségréguer les services présents sur cette machine. Toutefois, vers la fin du projet, notre hôte ESXi qui ne comportait que 8 GB de mémoire vive commençait à manquer de cette ressource matérielle et l'unique disque dur Western Digital Caviar Blue 5400 RPM 2.5" manquait cruellement d'IOPS pour opérer convenablement le système. Nous avons donc dû mettre tous les services Linux au sein de la même machine virtuelle, puisque plusieurs instances de CentOS, même sans environnement graphique, peuvent faire monter grandement la consommation de mémoire vive ainsi que d'IOPS et ce même si les services sont très légers à opérer.

Partie 1 : Activation du pare-feu

1. Activer le pare-feu pour laisser passer les connexions Samba. Si vous n'avez pas d'environnement graphique sur votre serveur, saisissez la commande suivante :

# CC	OMMANDE
------	---------

1 # system-config-firewall-tui

Cette commande affichera une simili-interface graphique pour le pare-feu. Cliquez sur Customize.



Cochez la case FTP en positionnant le curseur sur cette ligne et en appuyant sur la touche **SPACE**. Cliquez par la suite sur **Close**.



Cliquez sur OK.



Cliquez sur Yes.



Si vous disposez d'un environnement graphique, saisissez la commande suivante :

COMMANDE

1 # system-config-firewall

La fenêtre de configuration du pare-feu s'affichera. Après avoir **entré le mot de passe** root, cochez la case FTP puis cliquez sur **Apply**.

	Firewall Configurati	on	_ _ x
File Options Help			
Wizard Apply Relo	ad Enable Disable		
Trusted Services Other Ports	Here you can define which services an all hosts and networks.	e trusted. Trusted servio	ces are accessible from
Trusted Interfaces	Service ~	Port/Protocol	Conntrack Helper
Masquerading	Amanda Backup Client	10080/udp	amanda
Port Forwarding ICMP Filter	🗌 Bacula	9101/tcp, 9102/tcp, 9103/tcp	=
Custom Rules	🗌 Bacula Client	9102/tcp	
	DNS	53/tcp, 53/udp	
	✓ FTP	21/tcp	ftp
	IMAP over SSL	993/tcp	
	IPsec	/ah, /esp, 500/udp	
	Mail (SMTP)	25/tcp	
	Multicast DNS (mDNS)	5353/udp	
	Network Printing Client (IPP)	631/udp	
	Network Printing Server (IPP)	631/tcp, 631/udp	~
	Allow access to necessary service	s, only.	
The firewall is enabled. (modified)		

Partie 2 : Installation du service

1. Installez le service FTP.

```
# COMMANDE
```

- 1 **# yum install -y** vsftpd
- 2. Activez le service au démarrage et démarrez le service.

- 1 # /sbin/chkconfig --add vsftpd
- 2 # service vsftpd start

Partie 3 : Configuration du service

1. La configuration du serveur FTP se fait entièrement dans le fichier de configuration /etc/ vsftpd/vsftpd.conf.

Voici ici les lignes importantes à modifier.

Cette portion de texte définie que tous les usagers du serveur FTP doivent être authentifiés.

#	ТЕХТЕ
1	# Allow anonymous FTP? (Beware - allowed by default if you
2	comment this out).
3	anonymous_enable=NO
	La portion de texte suivante active les transferts en mode ASCII.

#	ТЕХТЕ
1	# By default the server will pretend to allow ASCII mode but
2	in fact ignore
3	# the request. Turn on the below options to have the server

#	ТЕХТЕ
4	actually do ASCII
5	<pre># mangling on files when in ASCII mode.</pre>
6	# Beware that on some FTP servers, ASCII support allows a
7	denial of service
8	<pre># attack (DoS) via the command "SIZE /big/file" in ASCII</pre>
9	mode. vsftpd
10	<pre># predicted this attack and has always been safe, reporting</pre>
11	the size of the
12	# raw file.
13	# ASCII mangling is a horrible feature of the protocol.
14	ascii_upload_enable=YES
15	ascii_download_enable=YES

Les deux lignes suivantes personnalisent la bannière d'accueil du serveur FTP lors d'une connexion.

#	ТЕХТЕ
1	# You may fully customise the login banner string:
2	ftpd_banner=Welcome to CentOS 6.5 Web FTP Service.

À la fin du fichier, on peut ajouter cette ligne si elle ne s'y retrouve pas :

```
# TEXTE
```

- 1 use_localtime=YES
- 2. Une fois la configuration effectuée, il faut redémarrer le serveur FTP.

COMMANDE

- 1 # service vsftpd restart
- 3. L'utilisateur *root* n'est pas autorisé à se connecter sur un serveur FTP. Il faut donc créer des utilisateurs pour utiliser le serveur.

#	COMMANDE
1	[root@mainserver ~]# useradd ftpuser1
2	[root@mainserver ~]# passwd ftpuser1
3	Changing password for user ftpuser1.
4	New password:
5	BAD PASSWORD: it is based on a dictionary word
6	Retype new password:
7	passwd: all authentication tokens updated successfully.

Partie 4 : test de la configuration

1. Pour **tester** la **connexion** en ligne de commandes, il faut **installer** le **client FTP** avec la ligne de commande suivante.

COMMANDE

1 **# yum install -y** ftp

 Il faut modifier une variable de SELinux afin que les utilisateurs puissent se connecter directement dans leur dossier personnel sur le serveur FGTP. Pour ce faire, exécutez la ligne cidessous.

COMMANDE

- 1 # setsebool -P ftp_home_dir on
- 3. Connectez-vous au serveur FTP.

COMMANDE

- 1 # ftp 10.0.3.248
- **2** Connected to 10.0.3.248 (10.0.3.248).
- 3 220 Welcome to CentOS 6.5 Web FTP Service.
- 4 Name (10.0.3.238:root): ftpuser1

#	COMMANDE
5	331 Please specify the password.
6	Password:
7	230 Login successful.
8	Remote system type is UNIX.
9	Using binary mode to transfer files.
10	ftp> pwd
11	257 "/home/ftpuser1"

Vous pouvez également tester la connexion FTP au travers d'un navigateur web.

Firefox *	×
Index of ftp://10.0.3.248/ +	
(() (t) ://10.0.3.248	☆ ▼ C Socgle P □ ▼ ↓ ↑
In days of the (140.0.2.2.40.1	
Index of ftp://10.0.3.248/	
Up to higher level directory	
Name	Size Last Modified
pub	2013-03-01 12:00:00 AM

Création d'un serveur NAS

NAS4Free est un système d'exploitation destiné au stockage mis réseau. Il est basé sur FreeBSD tout comme pfSense. Il est la solution libre pour faire compétition aux serveurs NAS que l'on retrouve dans les magasins qui dispose déjà de leur propre système d'opération, comme Synology ou QNap. NAS4Free peut donc transformer n'importe quel PC en NAS (*Network Attached Storage*). Le but d'un serveur NAS est de fournir un stockage distant ou un stockage central en entreprise. Un NAS dispose habituellement de plusieurs téraoctets de stockage réparti sur plusieurs disques durs en configuration RAID. C'est aussi l'endroit idéal pour utiliser des SSD pour faire une cache qui rendra la copie de fichiers plus rapide entre le client et le serveur. La beauté de ce système est qu'il est capable de fonctionner autant sur des PC plus vieux (32-bit), jusqu'au PC dernier cri équipée d'un processeur 64-bit. Il ne faut cependant pas espérer de grandes performances lors de l'utilisation sur un ancien PC. Mais il permet de facilement créer un espace pour faire des sauvegardes, ou de se faire soit même un *cloud* personnel lorsque combiné avec un DDNS (*Dynamic DNS*).

NAS4Free peu facilement se virtualisé, ce qui permet de le combiné sur un même serveur avec d'autres services.

De plus, NAS4Free nous servira aussi de serveur DHCP pour les besoins du projet

Paramètre	Réglage
Hardware Compatibility	Workstation/ESXi 10.0
CPU	2 Cores, no HT
RAM	512 MB
System HDD	2 GB, LSI Logic SAS, SCSI
Data HDD	64 GB, LSI Logic SAS, SCSI
Network Adapter	Bridged, connected directly to physical network. Connected at power on.
Virtualized Operating System	NAS4Free 9.2.0.1 (FreeBSD 9.2 x64)

Pour les besoins du projet, les configurations sont des plus minimalistes:

Partie 1 : Installation de NAS4Free

1. Après avoir **connecté l'ISO** de NAS4Free dans le lecteur CD/DVD virtuel, **démarrez** la machine.

Network bootrom is installed. Trying to boot from Primary Master IDE drive ... failed. Trying to boot from CD-ROM drive... CD Loader 1.2 Building the boot loader arguments Looking up /BOOT/LOADER... Found Relocating the loader and the BTX Starting the BTX loader BTX loader 1.00 BTX version is 1.02 Consoles: internal video/keyboard BIOS CD is cd0 BIOS drive A: is disk0 BIOS drive C: is disk1 BIOS 639kB/523200kB available memory FreeBSD/x86 bootstrap loader, Revision 1.1 (root@bake.isc.freebsd.org, Fri Sep 27 04:58:05 UTC 2013) Loading /boot/defaults/loader.conf /boot/kernel/kernel text=0xfa2290 data=0x33f190+0x113a28 syms=[0x8+0x17cf88+0x8+ 0x1d082a] /boot/kernel/zfs.ko size 0x23d298 at 0x1b43000 loading required module 'opensolaris' /boot/kernel/opensolaris.ko size 0x84d0 at 0x1d81000

NAS4Free: 9.2.0.1 (revision 943)

Build on: Mon Jan 20 08:51:18 CET 2014 Platform: x64-livecd Copyright (c) 2012-2013 The NAS4Free Project. All Rights Reserved. Visit: http://www.nas4free.org for system updates!

LAN Network IPv4 Address: 192.168.1.250 LAN Network Interface: em0

Now, the blank USB memory for installation can be inserted. To redisplay Console Menu, press enter key.

Console Menu

- 1) Configure Network Interfaces
- 2) Configure Network IP Address
- 3) Reset WebGUI Password
- 4) Reset to Factory Defaults
- 5) Ping Host 6) Shell

- 7) Reboot Server 8) Shutdown Server
- 9) Install/Upgrade from LiveCD/LiveUSB

Enter a number:

2. Maintenant que la machine est démarrée, appuyez sur 9 puis sur ENTER.

NAS4Free: 9.2.0.1 (revision 943) Build on: Mon Jan 20 08:51:18 CET 2014 Platform: x64-livecd Copyright (c) 2012-2013 The NAS4Free Project. All Rights Reserved. Visit: http://www.mas4free.org for system updates! LAN Network IPv4 Address: 192.168.1.250 LAN Network Interface: em0 Now, the blank USB memory for installation can be inserted. To redisplay Console Menu, press enter key. Console Menu 1) Configure Network Interfaces 2) Configure Network IP Address 3) Reset WebGUI Password 4) Reset to Factory Defaults 5) Ping Host 6) Shell 7) Reboot Server 8) Shutdown Server 9) Install/Upgrade from LiveCD/LiveUSB Enter a number: 9

Welcome to NAS4Free!

- 1. Boot NAS4Free in Normal Mode
- 2. Boot NAS4Free with ACPI enabled
- 3. Boot NAS4Free in Safe Mode
- 4. Boot NAS4Free with verbose logging
- 5. Escape to loader prompt
- 6. Reboot system

Select option, [Enter] for default or [Space] to pause timer 2 3. **Sélectionnez** la première option en appuyant sur **ENTER**.

	NAS4Free Install & Upgrade Options Menu		
<pre>i Install 'Embedded' OS on CF/USB Flash Drive or Hard Drive i Install 'Embedded' OS on HDD/Flash/USB + DATA + SWAP partition i Install 'Full' OS on HDD + DATA + SWAP partition i Upgrade 'Embedded' OS from LiveCD/LiveUSB i 5 Upgrade 'Full' OS from LiveCD/LiveUSB i 6 Upgrade and convert 'Full' OS to 'Embedded'</pre>			
	<_O <mark>K > < E</mark> xit >		

4. Faites **OK** en appuyant sur **ENTER.**

+		
NAS4Free 'Embedded' installer for CF, USB Flash Drive or HDD.		
- Create 1 partition for OS image - Uses a RAM disk to limit read/write access to the device		
WARNING: There will be some limitations: 1. This will erase ALL partitions and data on the destination disk 2. You can't use your destination disk for sharing data		
Installing on CF or USB Flash Drive is the preferred way: It saves you Power and a IDE/SATA/SCSI channel for more storage drives.		
Cancel>		

5. Sélectionnez la source de l'installation, dans notre cas, cd0 (CD-ROM).

<mark>≥d0</mark>	+
Cancel>	+

6. Sélectionnez la destination, **sélectionner** le disque de **2GB**.

Free OS should be instal	lled.
.0 65536MB <>	
	: :
	 +
<cancel></cancel>	++
	Free OS should be instal 65536MB <> (Cancel>

7. Une fois terminé, appuyez sur ENTER pour continuer.

Mount CDROM/USB. kern.geom.debugflags: 0 -> 16 Installing system image on device ada0. kern.geom.debugflags: 16 -> 0 Unmount CDROM/USB. NAS4Free has been installed on ada0. You can now safely remove the LiveCD/USB and reboot the server.

Press ENTER to continue.

8. Sélectionnez EXIT en utilisant les flèches et en appuyant sur ENTER.

9. Appuyez sur 7 puis sur **ENTER**.



10. Sélectionnez YES en appuyant sur ENTER, la machine redémarrera.

Do you really want to reboot the server?
<pre> Yes > < No > t </pre>

Déconnectez l'ISO de la machine virtuelle pour s'assurer que la machine démarre sur le disque dur.

Partie 2 : Configuration de NAS4Free

1. Une fois la machine redémarrée, **appuyez** sur **2** puis sur **ENTER**.

```
FreeBSD/amd64 (nas4free.local) (ttyv0)
Welcome to NAS4Free!
    NAS4Free: 9.2.0.1 (revision 943)
    Build on: Mon Jan 20 08:51:18 CET 2014 Platform: x64-embedded
    Copyright (c) 2012-2013 The NAS4Free Project. All Rights Reserved.
    Visit: http://www.nas4free.org for system updates!
        LAN Network IPv4 Address: 192.168.1.250
        LAN Network Interface:
                                  em⊙
Console Menu
1) Configure Network Interfaces
2) Configure Network IP Address
3) Reset WebGUI Password
4) Reset to Factory Defaults
5) Ping Host
6) Shell
7) Reboot Server
8) Shutdown Server
Enter a number: 2
```

 Il vous sera alors demandé si vous désirez configurer l'interface réseaux par DHCP, sélectionner NO puisqu'il est préférable de configurer une adresse IP statique pour ce genre de service.



3. **Entrez** alors une adresse IP faisant partie de votre plage réseau. Pour le projet, nous sommes donc sur le réseau 10.0.1.X.

Enter new LAN IPv4 address.	+ !
+	
	+

4. Entrez l'adresse IP de la passerelle par défaut, pour nous ce sera l'adresse IP de pfSense.

Enter IPv4 defau +	ult gateway.	+
¦10.0.1.1∎ ⁺		; +
<mark>< 0K ></mark>	<cancel></cancel>	+

5. Entrer l'adresse du serveur DNS, pour nous une fois de plus, ce sera celle de pfSense.

Enter DNS IPv4 +	address.	+ +	
< <u>0k</u> >	<cancel></cancel>	+ +	

6. Il vous sera demandé si vous désirez configurer **IPv6** sur cette interface. Sélectionnez **NO**.

7. Une fois l'interface **configurée**, appuyez sur **ENTER** pour continuer.

Initializing interface. Please wait...

The IP address has been set to: LAN Network IPv4 Address: 10.0.1.12/24

You can access the WebGUI using the following URL: http://10.0.1.12

Press ENTER to continue.

8. Maintenant, le NAS est accessible par un **navigateur web.** Tapez l'adresse IP précédemment configurée dans la barre d'adresse.



9. Tapez alors « admin » dans le champ Username puis « nas4free » dans le champ Password.



10. Vous serez alors dirigé vers l'interface de statut de NAS4Free.

)	nas4free.local - System information	
) 🖶 🛆 🕑 📂 💽 + 📀 10.0.1.12	2/index.php	C Lecter
10 Minute Mail 2048 NAS4Free Portail Cmor	ntmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevy ng Diagram	
	<u> </u>	nastir
stem Network Disks Services Acces	s Status Diagnostics Advanced Help	
System information		
Hostname	nas4free.local	
Version	9.2.0.1 - Shigawire (revision 943)	
Build date	Mon Jan 20 08:51:18 CET 2014	
Platform OS	FreeBSD 9.2-RELEASE-p3 (kern.osreldate: 902001)	
Platform	x64-embedded on Intel(R) Core(TM) i7-4750HQ CPU @ 2.00GHz	
System	Parallels Software International Inc. Parallels Virtual Platform	
System bios	Parallels Software International Inc. version: 9.0.24172.951362 Tue, 03 Dec 2013 19:24:49	
System time	Tue May 6 14:52:53 UTC 2014	
System time System uptime	Tue May 6 14:52:53 UTC 2014 3 minute(s) 4 second(s)	
System time System uptime Last config change	Tue May 6 14:52:53 UTC 2014 3 minute(s) 4 second(s) Tue May 6 14:40:52 UTC 2014	
System time System uptime Last config change CPU usage	Tue May 6 14:52:53 UTC 2014 3 minute(s) 4 second(s) Tue May 6 14:40:52 UTC 2014 0%	
System time System uptime Last config change CPU usage Memory usage	Tue May 6 14:52:53 UTC 2014 3 minute(s) 4 second(s) Tue May 6 14:40:52 UTC 2014 0% 33% of 244MiB	
System time System uptime Last config change CPU usage Memory usage Load averages	Tue May 6 14:52:53 UTC 2014 3 minute(s) 4 second(s) Tue May 6 14:40:52 UTC 2014 0% 33% of 244MiB 0.21, 0.32, 0.15 [Show process information]	
System time System uptime Last config change CPU usage Memory usage Load averages Disk space usage	Tue May 6 14:52:53 UTC 2014 3 minute(s) 4 second(s) Tue May 6 14:40:52 UTC 2014 0% 33% of 244MiB 0.21, 0.32, 0.15 [Show process information] No disk configured	

Copyright © 2012-2014 The NAS4Free Project

11. Sélectionnez General sous l'onglet System.

00		nas4free.local – System information	H2			
) 🖶 🛆 🖭 🖻 🔘 🕂 🚱 10.0.1.12/inde	x.php c Le	cteur			
□ ■	10 Minute Mail 2048 NAS4Free Portail Cmontmore	ncy Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	+			
			as4free.local			
Sys	stem Network Disks Services Access S	tatus Diagnostics Advanced Help				
Ger Adr Fin	neral avanced <u>General</u> mware - Jung Restore					
Fac	tory defaults	nastfree local				
Re	poot	Security Shipawire (revision 943)	-			
Shi	utdown	Mon Jan 20 08:51:18 CET 2014	-			
Log	gout	FreeBSD 9.2-RELEASE-p3 (kern.osreldate: 902001)	-			
	Platform	x64-embedded on Intel(R) Core(TM) i7-4750HQ CPU @ 2.00GHz	-			
	System	Parallels Software International Inc. Parallels Virtual Platform				
	System bios	Parallels Software International Inc. version: 9.0.24172.951362 Tue, 03 Dec 2013 19:24:49				
	System time	Tue May 6 14:52:59 UTC 2014				
	System uptime	3 minute(s) 10 second(s)	-			
	Last config change Tue May 6 14:40:52 UTC 2014					
	CPU usage	0%	_			
	Memory usage	33% of 244MiB				
	Load averages	0.19, 0.31, 0.15 [Show process information]				
	Disk space usage	No disk configured				
	UPS Status	UPS disabled [Show ups information]				

Copyright © 2012-2014 The NAS4Free Project

12. Il vous sera alors possible de **changer** la **langue** si vous le désirez.

00		nas4free.local – System General Setup	H.
	🖶 🛆 🖭 🖻 💽 + 🚱 10.0.1.3	2/system.php & C	ur 🔘
	10 Minute Mail 2048 NAS4Free Portail Cmg	ntmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	+
	The Free Nelwork Attached Storage Project		iree.local
Syste	em Network Disks Services Acce	is Status Diagnostics Advanced Help	
S) d	ystem General Setup General Password		
	WebGUI		
	Username	admin It's recommended to change the default username and password for accessing the WebGUI, enter the username here.	
	Protocol	HTTP = : Select Hypertext Transfer Protocol (HTTP) or Hypertext Transfer Protocol Secure (HTTPS) for the WebGUI.	
	Port	Enter a custom port number for the WebGUI if you wint to override the default (80 for HTTP, 443 for HTTPS).	
	Language	French ±) Select the language of the WebGUI.	
	Hostname		
	Hostname	nas4free Name of the NAS host, without domain part e.g. <i>nas4free</i> .	'
	Domain	local e.g. com, local	
DNS settings			
	IPv4 DNS servers	10.0.1.1	
		IPv4 addresses	
		Copyright © 2012-2014 The NAS4Free Project	
13. Descendez un peu plus bas, et cliquez sur **Save**.

	nas4free.local – System General Setup	
	0.0.1.12/system.php	C Lecteur
10 Minute Mail 2048 NAS4Free Port	ill Cmontmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	
The Free Network Atlached Storage Proj	n oct	nas4free.
em Network Disks Services	Access Status Diagnostics Advanced Help	
Language	French	
	Select the language of the WebGUI.	
Hostname		
Hostname	nas4free	
	Name of the NAS host, without domain part e.g. nas4free.	
Domain	local	
	e.g. com, local	
DNS settings		
IPv4 DNS servers	10.0.1.1	
	IPv4 addresses	
IPv6 DNS servers		
	IPVo addresses	
Time		
Time zone	Etc/UTC ÷	
	Select the location closest to you.	
System time		
	Enter desired system time directly (format mm/dd/yyyy hh:mm) or use icon to select it.	
Enable NTP	Use the specified NTP server.	
Save		
•	Convolution 2017 2014 The NASAGree Devicet	

14. Cliquez sur Mot de passe, pour changer le mot de passe par défaut, à des fins de sécurité.

00		nas4free.local – System General Setup	
▲ ▶ [r]	🖶 🛆 🕑 📂 💽 🕂 😚 10.0.1.	12/system.php	🖒 Lecteur
CC IIII 1	0 Minute Mail 2048 NAS4Free Portail Cm	ontmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	1
	The First Network Attached Storage Project		nas4free.local
Systen	n vices Acce	ss Status Diagnostics Advanced Help	_
Sve	stem i General Setun		
J J	Stemp General Setap		
Ge	neral Password		
	WebCHT		
	Webdol		_
	Username	admin	
-		It's recommended to change the default username and password for accessing the webgui, enter the username nere.	
	Protocol	HTTP :	
_		Select Hypertext Transfer Protocol (HTTP) or Hypertext Transfer Protocol Secure (HTTPS) for the WebGUI.	
	Port		
		Enter a custom port number for the WebGUI if you want to override the default (80 for HTTP, 443 for HTTP5).	
	Language	French ÷	
		Select the language of the WebGUI.	
	Hostname		_
	Hostname	nas4free	
		Name of the NAS host, without domain part e.g. nas4free.	
	Domain	local	
		e.g. com, local	
	DNS sottings		
	TLAT DIAD SELAGLE	10.0.1.1	
		To deallance	
		1744 duuresses	

15. Entrer « **nas4free** » dans le champ *Mot de passe actuel*, puis votre **nouveau mot de passe** dans les deux champs inférieurs. Cliquez ensuite sur **Enregistrer**.

		nacéfree local - SystèmelCénérallMot de nasse	
<image/>		2/system_password.php	C Lecteur
	III 10 Minute Mail 2048 NAS4Free Portail Cmc	ntmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	[+
Système Réseau Disques Services Accès Statut Diagnostics Avancé Alde Système Général Mot de passe Filter Red Passe actuel Filter Red Passe	The Free Network Attached Storage Project	ا	nastfree.local
Système J Général J Mot de passe Interface Web	Système Réseau Disques Services Ac	cès Statut Diagnostics Avancé Aide	
Interface Web Mureau mot de passe Suvais sublatez changer le mot de passe d'accès à l'Interface web, entrer-le la deux fus. Enregistrer Nomeau mot de passe ent bien le mot de passe rote par défaut du système!	Système Général Mot de passe		
Interface Web Mod de passe actuel Nouveau mod de passe S vous souhatez changer le mot de passe d'accès à l'interface web, entrec·le ki deux fois. Note: • Le nouveau mot de passe est bien le mot de passe root par défaut du système!			
Mot de passe actuel	Interface Web		
Nouveau mot de passe Image: Strate in the image:	Mot de passe actuel		
Si vous souhaltez changer le mot de passe d'accès à l'interface web, entrez-le id deux fois.	Nouveau mot de passe	(Confirmation)	
Erregistrer Nete • Le nouveau mot de passe est bien le mot de passe root par défaut du système!		Si vous souhaitez changer le mot de passe d'accès à l'interface web, entrez-le ici deux fois.	
Note: • Le nouveau mot de passe est bien le mot de passe root par défaut du système!	Enregistrer		
	Note:	t are défaut du quitàmal	
	Le nouveau mot de passe est bien le mot de passe roc	t par deraut ou systeme!	

Vous aurez alors la confirmation que le changement a été sauvegardé.

	nas4free.local – Système Général Mot de passe	¢ lecteur 0
10 Minute Mail 2048 NAS4Free Portail Cmor	tmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	+
The Free Network Alfached Storage Project	<u>e</u>	nas4free.local
Système Réseau Disques Services Acc	ès Statut Diagnostics Avancé Aide	
Système Général Mot de passe		
Les modifications ont été appliquées avec suo	ės.	
Interface Web		
Mot de passe actuel		
Nouveau mot de passe	(Confirmation) Si vous souhaitez changer le mot de passe d'accès à l'interface web, entrez-le ici deux fois.	
Enregistrer		
Note: • Le nouveau mot de passe est bien le mot de passe root	par défaut du système!	
	Copyright © 2012-2014 The NAS4Free Project	

Partie 3 : Configuration des disques

1. Cliquez sur Gestion sous l'onglet Disques.



Copyright © 2012-2014 The NAS4Free Project

2. Cliquez sur Importer des disques.



3. Vos disques durs apparaîtront, dans notre cas: le disque de 2GB avec l'OS et l'autre de 64GB pour des fins de stockage. Cependant, ce dernier n'est pas encore formaté.

			12/11-1-		nas4free.l	ocal – Disques Gestion				A 1	
	副していていていていていていていています。 O Minute Mail	2048 NAS4Free Portail Cm	12/disks_m	anage.php • Col.Net Outlook YouTube	Facebook	Apple iCloud Opendp Enva	to Marketplace:	2004 Chevy	.ng Diagram	C Lecteur	
										nas4free	e.local
Systèm	ne Réseau	Disques Services Ac	cès Sta	atut Diagnostics Avancé	Aide	_	_	_	_	_	
Disc	ques Ges	tion									
Ges	stion S.M.A.F	R.T. Initiateur iSCSI									
		o dianuas continuo dés									
		s aisques sont importes.									
ľ	Périphérique	Modèle d'appareil	Taille	Numéro de série	Controller	Controller model	Délai de mise en veille	Système de fichiers	Statut		
a	ada0	Nas4Free-0 SSD	2048MB	XQB96T9083R4Z7T8V0S5	ata0	Intel ICH2 UDMA100 controller	Toujours actif	UFS	CONNEC	4 💢	
a	ada1	Nas4Free-1 SSD	65536MB	1Z8W05KDJ564966C8F3B	ata1	Intel ICH2 UDMA100 controller	Toujours actif	Inconnu ou non formaté		4 💢	
										+	
	Importer des di	sques Effacer la configuration a	ictuelle et ir	nporter les disques Rebalayer les	s disques						
	Importer des di	sques raid logiciel Effacer la co	nfiguration	actuelle et importer les disques raid	logiciel						
	_		_		Copyright © 2	2012-2014 The NAS4Free Project	_	_	_	_	

4. Cliquez sur **Formater** sous l'onglet **Disques**.

0 	r) 🖻 💽 + 🕑 10.0	.1.12/disks_m	anage.php	nas4free.l	ocal - Disques Gestion				Č Lecteur
10 Minute Mail	2048 NAS4Free Portail	Cmontmorency	/ Col.Net Outlook YouTube	Facebook	Apple iCloud Opendp Enva	to Marketplace	s 2004 Chevy	ng Diagram	nas4free.lo
ystème Réseau Disques Ges Gestion S.M.A.	Disques Services Gestion RAID logical Chiffrement Chiffrement ZFS Formater Point de montage Formater Sidques sont importe Formater	Accès Sta	atut Diagnostics Avancé	Aide					
Périphérique	Modèle d'appareil	Taille	Numéro de série	Controller	Controller model	Délai de mise en veille	Système de fichiers	Statut	
ada0 ada1	Nas4Free-0 SSD Nas4Free-1 SSD	2048MB 65536MB	XQB96T9083R4Z7T8V0S5 1Z8W05KDJ564966C8F3B	ata0 ata1	Intel ICH2 UDMA100 controller Intel ICH2 UDMA100 controller	Toujours actif	UFS Inconnu ou non	CONNECTE	4 🗙
Importer des d	Importer des disques Effacer la configuration actuelle et importer les disques Rebalayer les disques Inter les disques							+	
				Copyright @ 2	2012-2014 The NAS4Free Project				

5. Sélectionnez le **disque dur à formater** avec le menu déroulant, et indiquez-lui un nom. **ATTENTION*** Ne pas sélectionner le disque contenant le système NAS4Free.

0 0 0 nas	s4free.local - Disques Formater
(▲) ►) ⊕ △ 𝔄 𝔅 𝔅 𝔅 (𝔅) + 𝔅 10.0.1.12/disks_init.php	C Lecteur
10 Minute Mail 2048 NAS4Free Portail Cmontmorency Col.Net Outlook YouTube Fac	ebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram
The Free Network Atlached Storage Project	nas4free.local
Système Réseau Disques Services Accès Statut Diagnostics Avancé A	lide
Disques Formater Disque ada1: 65536MB 0 ÷ Système de fichiers UFS (GPT and Soft Updates) ÷ Étiquette de volume NASDATA Étiquette de volume NASDATA	
Espace disque minimum 8 ÷ Indiquez le pourcentage d'espace disque inaccessible a	ux utilisateurs normaux. Notez qu'abaisser ce seuil peut nuire aux performances et à l'auto-défragmentation.
Format avancé 💿 Activer le format avancé (secteur de 4 KOctets)	
Ne pas effacer le MBR Conserver le MBR intact (utile avec certains contrô	leurs RAID)
Formater le disque	

Copyright © 2012-2014 The NAS4Free Project

6. Du texte défilera alors au bas de la page, lorsque complété, la dernière ligne sera marqué *Terminé!*



7. Sélectionnez Point de montage sous l'onglet Disques.



8. Cliquez sur le symbole « + » pour ajouter un point de montage.

	nas4free.local	– Disques Point de montage Ge	estion		¢ Lecteur O
III 10 Minute Mail 2048 NAS4Free Portail Cmontmorency Col.	Net Outlook YouTube Facebo	ok Apple iCloud Opendp E	Envato Marketplaces 2004 Chevyng D	Diagram	nas4free.local
Système Réseau Disques Services Accès Statut Disques Point de montage Gestion Gestion Outlis Fack	Diagnostics Avancé Aide				_
Disque	Système de fichiers	Nom	Description	Statut	
Avertissement: UFS and ZFS are the NATIVE filesystems of FreeBSD (the underlying OS of NA	S4Free). Attempting to use other filesyst	ems such as FAT, FAT32, EXT2, EXT3, EX	CT4 or NTFS can result in unpredictable results, f	ile corruption, and loss of uata!	•

9. Sélectionnez le disque dur de stockage dans le menu déroulant. Donnez-lui un nom et une description.



10. Descendez plus bas et cliquez sur Ajouter.

The Free Network Attached Storage Pro	O Njøct		I A A A A A A A A A A A A A A A A A A A	
me Réseau Disques Service	s Accès Statut Diagnostics CD/DVDsi vous voulez monter un	Avancé Aide lecteur CD/DVD.	_	_
Numéro de partition	1			
Système de fichiers	UFS ‡			
Nom du point de montage	NAS4Free_DATA			
Description	Nas Data Vous pouvez saisir ici une descriptic	on pour votre référence.		
Lecture seule	Monter le système de fichiers e	en lecture seule (même le super-utilisateur ne pourra pas y é	crire).	
Vérification de système de fichier	Activer la vérification de consist	tance de système de fichier avant-plan/arrière-plan durant la	a procédure de démarrage.	
Restrictions d'accès				
Propriétaire	root \$			
Groupe	wheel \$			
Mode		Lecture	Écriture	Exécuter
	Propriétaire	✓	I	S
	Groupe	S	٢	٢
	Autres		ď	۷
Aiguter Appuler				

11. Un message vous dira que la configuration a été modifiée, cliquez sur Appliquez les modifications.

	nas4free.local	- Disques Point de montage Ge	estion		
H H	hp Net Outlook YouTube Facebo	ok Apple iCloud Opendp I	Envato Marketplaces 2004 Chevyng Diag	ram	C Lecteur
The Free Network Attached Storage Project			ł		nas4free.local
Système Réseau Disques Services Accès Statut	Diagnostics Avancé Aide	3	_	_	_
Disques Point de montage Gestion Gestion Outils Fack Image: Straight of the s	-	-			
Appliquer les modifications					
Disque	Système de fichiers	Nom	Description	Statut	Co 🏎
/dev/ufsid/5368f8c823caffe7 (ada1p1)	ufs	NAS4Free_DATA	Nas Data	Initialisation	4° 👗
Avertissement: UFS and ZFS are the NATIVE filesystems of FreeBSD (the underlying OS of NA	S4Free). Attempting to use other filesyste	ams such as FAT, FAT32, EXT2, EXT3, E)	KT4 or NTFS can result in unpredictable results, file o	orruption, and loss of data!	Ť
	Convrig	ht © 2012-2014 The NAS4Free Project			

12. Votre disque sera alors pleinement configuré.

00	nas4free.local	– Disques Point de montage Ge	estion		
▶ 🖶 △ 🔟 🖻 🔘 + 📀 10.0.1.12/disks_mount.ph	1p				C Lecteur
The Free Network Alfached Storage Project	let Outlook YouTube Facebo	ok Apple iCloud Opendp E	Envato Marketplaces	2004 Chevyng Diagram	nas4free.local
Système Réseau Disques Services Accès Statut	Diagnostics Avancé Aide)			
Disques Point de montage Gestion Gestion Outils Fack					
Disque	Système de fichiers	Nom	Description	Statut	
/dev/ufsid/5368f8c823caffe7 (ada1p1)	ufs	NAS4Free_DATA	Nas Data	ОК	A 🗙

Partie 4 : Configuration d'un partage Windows sur NAS4Free

1. Cliquez sur CIFS/SMB sous l'onglet Services.



Copyright © 2012-2014 The NAS4Free Project

2. Cochez la case **Activer**. **Sélectionnez Login local** dans le premier menu déroulant. Puis vous pouvez mettre une description dans le champ prévu.

	nas4free.local - Services CIFS/SMB Réglages	Č Lecteur
10 Minute Mail 2048 NAS4Free	Portail Cmontmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	+
	e Project	nas4free.local
Système Réseau Disques Serv	rices Accès Statut Diagnostics Avancé Aide	
Samisos CIES /SMR Dági	2000	
Bédlager Battage	ayes	
Regiages Partages		
Common Internet File System (CIFS)		Activer
Authentification	Login local 💠	
Protocole Maximum	SMB2 ÷) SMB2 est pour les récents système d'exploitation comme Windows 7 et Vista. NT1 est pour l'ancien système d'exploitation comme XP.	
Nom NetBIOS	nas4free	
Groupe de travail (workgroup Window	WS) WORKGROUP Le groupe de travail dans lequel le serveur apparaît lorsqu'il est interrogé par Windows ou clients SMB (maximum 15 caractères).	
Interface	Toutes les interfaces ÷	
Description	NAS4Free Server	
Jeu de caractères Dos	CP437 (Latin US) +	
Jeu de caractères Unix	UTF-8 ÷	
Niveau de journalisation	Minimum	
Maître explorateur local	Oui ÷ Permet au serveur d'essayer de s'enregistrer comme maître explorateur local.	
Serveur de temps	Oui ≑) Le serveur se présente comme un serveur de temps pour les clients Windows.	

3. Descendez plus bas sur la page et appuyez sur **Enregistrer** et **redémarrez le système.**

00	nas4free.local – Services CIFS/SMB Réglages	
	0.1.12/services_samba.php	C Lecteur
10 Minute Mail 2048 NASAFree Portail	Cmontmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	nas4free.local
Système Réseau Disques Services	Accès Statut Diagnostics Avancé Aide Taille du tampon d'envoi (64240 par défaut).	
Taille du tampon de réception	64240 Taille du tampon de réception (64240 par défaut).	
Lecture/écriture élargie	Activer la lecture/écriture élargie Utiliser les nouvelles requêtes SMB lecture/écriture en streaming 64k apparues avec Windows 2000.	
Utiliser sendfile	Activer l'utilisation de sendfile. Cela peut permettre d'utiliser le CPU plus efficacement et rendre Samba plus rapide. Samba le désactive automatiquement pour les clients utilisant un protocole plus ancien que NT LM 0.12 et détecte un client Windows 9.x.	: lorsqu'il
Support EA	Activer le support des attributs étendus Autoriser les clients à tenter de stocker des attributs étendus OS/2 sur un partage.	
Stocker les attributs DOS	Activer les attributs de stockage DOS Si ce paramètre est activé, Samba essaye en premier de lire les attributs DOS (Système, Caché, Archive ou Lecture seule) depuis un attribut étendu du système de fichiers, avant de traduire le DOS en bits de permission UNIX. Lorsqu'ils sont définis, les attributs DOS sont stockés comme un attribut étendu du système de fichiers UNIX, associé au fichier ou répertoire.	es attributs
Mots de passe vides	Autoriser l'accès client aux comptes ayant un mot de passe vide	
E/S asynchrones (AIO)	Activer les E/S asynchrones (AIO)	
Paramètres auxiliaires	Ces paramètres sont ajoutés à la section [Global] de smb.conf. Veuillez consulter la documentation.	
Enregistrer et redémarrer Note: Pour augmenter les performances de CIFS, essayez o • Activer 'LyS asynchrones (AIO)' • Activer 'Lecture/forture élargie' • Activer la 'Personnalisation'		
	Copyright © 2012-2014 The NAS4Free Project	_

4. Vous aurez alors la confirmation que tout a été enregistré. Appuyez ensuite sur **Partages**.

00		nas4free.local – Services/CIFS/SMB/Réglages	1 ²
	(➡) (⊡) (⊡) (●) (+ (●) 10.0.1	.12/services_samba.php	C Lecteur
	10 Minute Mail 2048 NAS4Free Portail Cm	nontmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram	
			nas4free.local
Syst	ème Réseau Disques Services A	ccès Statut Diagnostics Avancé Aide	
S	ervices CIFS/SMB Réglas Réglages Partages Les modifications ont été appliquées avec s	ucès.	
	Common Internet File System (CIFS)		▲ Activer
	Authentification	Login local ÷	
	Protocole Maximum	SMB2 SMB2 SMB2 SMB2 est pour les récents système d'exploitation comme Windows 7 et Vista. NT1 est pour l'ancien système d'exploitation comme XP.	
	Nom NetBIOS	nas4free	
	Groupe de travail (workgroup Windows)	WORKGROUP Le groupe de travail dans lequel le serveur apparaît lorsou'il est interrogé par Windows ou clients SMB (maximum 15 caractères).	
	Interface	Toutes les interfaces 💠	
	Description	NAS4Free Server Description du serveur. Ce champ peut rester vide.	
	Jeu de caractères Dos	CP437 (Latin US) +	
	Jeu de caractères Unix	UTF-8 ÷	
	Niveau de journalisation	(Minimum +)	
	Maître explorateur local	Oui ÷	
		Permet au serveur d'essaver de s'enreoistrer comme maître exolorateur local,	
		CODVIDUE OF ZU12-ZU14 THE WASHING PROPER	

5. **Inscrivez** un **nom** puis un **commentaire** pour le **partage Windows**, puis cliquez sur le bouton « ... » pour indiquer l'emplacement du partage

	nas4free.local - Services CIFS/SMB Partage Ajouter
10 Minute Mail 2048 NASAEree Porta	NUTLIE/SetVice_amba_state_eutchptp Courtons YouTube Earshook Apple (Court Onendo Envato Markstolaces 2004 Chevy no Diagram
ème Réseau Disques Services	Accès Statut Diagnostics Avancé Aide
ervices CIFS/SMB Partage	Ajouter
Nom	Windows_Share
Commentaire	Partage Windows
Chemin d'accès	Chemin à partager.
Lecture seule	En lecture seule Si ce paramètre est activé, les utilisateurs n'auront pas le droit de créer ou modifier des fichiers du partage.
Navigable	☑ Rendre naviguable Contrôle si ce partage doit apparaître dans la liste des partages disponibles et navigables depuis la vue réseau du client.
Invité	Ceci contrôle si le partage est accessible par le compte invité.
Héritage des permissions	Activer l'héritage des permissions Les permissions pour de nouveaux fichiers et répertoires sont normalement gérées en créant un masque et un masque de répertoire mais le paramètre d'héritage des permissions prend le dessus. Ceci peut être particulièrement utile pour des systèmes avec beaucoup d'utilisateurs, de manière à ce qu'un seul partage puisse être utilisé d'une manière flexible par chaque utilisateur.
Poubelle	Ceci créera une poubelle dans le partage.
Cacher les fichiers commençant par un point	Ce paramètre vérifie si les fichiers débutant par un point apparaissent comme fichiers cachés.
Cliché Instantané	 ✓ Activer le diché instantané Ceci fourni une copie fantome créée par un instantané automatique (ZFS uniquement).
Format du cliché instantané	auto-%Y%m%d-%H%M%S Le format personnalisé de l'instantané pour le service cliché instantané peut être spécifié. Le format par défaut est auto-%Y%m%d-%H%M%S utilisé pour la canture automatique 7FS.

6. Cliquez sur le répertoire, dans notre cas NAS4Free_DATA.

) O nas4free.local - Services CIFS/SMB Partage Ajouter				
10. IIII 10 Minute Mail 2048 NAS4Free Portail	Cmontmorency Col.Net	Outlook YouTube Facebook Apple i	Cloud Opendp Envato Marketplace	es 2004 Chevyng Diagram	
The Free Network Attrached Storage Project	M I			The sector	ee.local
Système Réseau Disques Services	Accès Statut Di	agnostics Avancé Aide			
	00	Sélectionneur de fichier	M		
Services CIFS/SMB Partage	/mnt		Ok Cancel		
Réglages Partages					
	Name	Size Type Last Modifie	d		
Nom	1 NAS4Free_DATA	-	4 2:59 PM		
Commentaire		U Dyte			
Chemin d'accès					
Lecture seule			e.		
Navigable			seau du client.		
Invité					
Héritage des permissions	Les permissions pour o peut être particulièrem	les permissions le nouveaux fichiers et répertoires sont normalement vent utile pour des systèmes avec beaucoup d'utilisate	gérées en créant un masque et un masque o surs, de manière à ce qu'un seul partage puis	de répertoire mais le paramètre d'héritage des permissions prend le dessus. Ceci se être utilisé d'une manière flexible par chaque utilisateur.	
Poubelle	 Activer la corbeille Ceci créera une poube 	lle dans le partage.			
Cacher les fichiers commençant par un point	🗹 Ce paramètre véri	fie si les fichiers débutant par un point apparaissent c	omme fichiers cachés.		
Cliché Instantané	Activer le cliché in Ceci fourni une copie f	stantané antome créée par un instantané automatique (ZFS ur	liquement).		
Format du cliché instantané	auto-%Y%m%d-%H Le format personnalisé	%M%S i de l'instantané pour le service cliché instantané peut	être spécifié. Le format par défaut est auto-	%Y%m%d-%H%M%S utilisé pour la capture automatique ZFS.	
		Copyright © 2012-2014 T	he NAS4Free Project		

7. Cliquez sur OK.

000	nas4free.local – Services CIFS/SM	B Partage Ajouter	H.
	12/services_samba_share_edit.php	C Lecteur	0
	ontmorency Collect Outlook YouTube Facebook Apple (Cloud	Openop Envato Marketplaces 2004 Chevying Diagram	+
Système Réseau Disques Services A	ccès Statut Diagnostics Avancé Aide		
Services CIFS/SMB Partage Aj	outer		
Réglages Partages	⊖ ⊖ ⊙ Sélectionneur de fichier	and the second sec	
Nom	/mnt/NAS4Free_DATA/	OK	
Commentaire	Name Size Type L Parent Directory O bytes	ast Modified	
Chemin d'accès	C		
Lecture seule	S		
Navigable	C	lient.	
Invité	e c		
Héritage des permissions	e Li P	que de répertoire mais le paramètre d'héritage des permissions prend le dessus. Ceci e puisse être utilisé d'une manière flexible par chaque utilisateur.	
Poubelle	Ceci créera une poubelle dans le partage.		
Cacher les fichiers commençant par un point	Ce paramètre vérifie si les fichiers débutant par un point apparaissent comme f	ichiers cachés.	
Cliché Instantané	 Activer le cliché instantané Ceci fourni une copie fantome créée par un instantané automatique (ZFS uniqueme 	nt).	
Format du cliché instantané	auto-%Y%m%d-%H%M%S Le format personnalisé de l'instantané pour le service cliché instantané peut être sp	écífié. Le format par défaut est auto-%Y%m%d-%H%M%S utilisé pour la capture automatique ZFS.	
	Copyright © 2012-2014 The NAS4	Free Project	

8. Descendez plus bas sur la page et **cliquez** sur **Ajouter**.



9. Vous aurez alors la confirmation que tout a été enregistré, cliquez sur **Appliquez les modifications**.

		nas4free.local – Servi	ces CIFS/SMB Partages		Lortour
	10 Minute Mail 2048 NAS4Free Portail Cmontmorency Co	.Net Outlook YouTube Facebook Apple	iCloud Opendp Envato Marketplaces	2004 Chevyng Diagram	+
					nas4free.local
Syst	eme Réseau Disques Services Accès Statut	Diagnostics Avancé Aide			
S	ervices CIFS/SMB Partages				
	La configuration a été modifiée. Vous devez appliquer les changements afin qu'ils prennent effet. Appliquer les modifications				
	Chemin d'accès	Nom	Commentaire	Navigable Invité	
	/mnt/NAS4Free_DATA/	Windows_Share	Partage Windows	Oui Oui	A 💢
					+

Copyright © 2012-2014 The NAS4Free Project

Vous aurez la confirmation de l'application.



Partie 5 : Configuration d'un compte utilisateur

1. Cliquez sur Utilisateur et groupes sous l'onglet Accès

	nas4free.local - Servio	ces CIFS/SMB Partages			C Lecteur
Image: Contract of the second seco	let Outlook YouTube Facebook Apple	iCloud Opendp Envato Marketplaces 2	2004 Chevyng Diagr	am	· · · · · · · · · · · · · · · · · · ·
The Free Network Atlached Storage Project					nas4free.local
Système Réseau Disques Services Accès Statut	Diagnostics Avar é Aide		_	_	_
Services CIFS/SMB Partages Active Directory Réglages Partages	Utilisateurs et gra				
Les modifications ont été appliquées avec succès.					
Chemin d'accès	Nom	Commentaire	Navigable	Invité	
/mnt/NAS4Free_DATA/	Windows_Share	Partage Windows	Oui	Oui	4° 🗙
					T.

2. Cliquez sur le symbole « + » pour ajouter un utilisateur.

● ● ● ● ● ● ●	.0.1.12/access_users.php	nas4free.local – Accès	Utilisateurs		Č Lecteur
	Il Cmontmorency Col.Net Outlook	YouTube Facebook Apple iClo	ud Opendp Envato Marketpl	aces 2004 Chevyng Diagram	
Système Réseau Disques Services	ct Accès Statut Diagnostics	Avancé Aide			nas4free.local
Accès Utilisateurs Utilisateurs Groupes					
Utilisateur	Nom complet		UID Groupe		
					+

3. Inscrivez un nom d'utilisateur, puis le nom complet et un mot de passe.

	nas4free local – Arcèsil Itilisateurs/Aiouter	<u>م</u>
	2/arress users edit nhn	Č Lecteur
m III 10 Minute Mail 2048 NAS4Free Portail Cm	antenergy Collect Outlook YouTube Farebook Apple iCloud Opendo Envato Marketolaces 2004 Chevy on Diagram	
The Free Network Alfached Storage Project		nas4free.local
Système Réseau Disques Services Ac	cès Statut Diagnostics Avancé Aide	
Accès Utilisateurs Ajouter		
Nom	utilisateur1 Nom de l'utilisateur (login).	
Nom complet	test Nom complet de l'utilisateur.	
Mot de passe	••••••• (Confirmation) Mot de passe. •••••••	
Identifiant de l'utilisateur	1000 Identifiant numérique de l'utilisateur.	
Shell	nologin : 2 Le shell de login de l'utilisateur.	
Groupe principal	guest Configure le groupe principal de l'utilisateur.	
Groupe additionnel	admin audit authpf bin bin bind daeron dialer ftp games guest Choisir des groupes supplémentaires pour ce compte.	
	Copyright © 2012-2014 The NAS4Free Project	

4. Descendez plus bas et cliquez sur Ajouter.

10 Minute Mail 2048 NAS4Free P	nas4free.local - Accès Utilisateurs Ajouter 10.0.1.12/access_users_edit.php ctail Cmontmorency Col.Net Outlook YouTube Facebook Apple iCloud Opendp Envato Marketplaces 2004 Chevyng Diagram
The Free Network Attached Storage f	e [™] rojoct
stème Réseau Disques Servio	es Accès Statut Diagnostics Avancé Aide
Nom complet	test
Mot de passe	(Confirmation) Mot de passe.
Identifiant de l'utilisateur	1000 Identifiant numérique de l'utilisateur.
Shell	nologin e) Le shell de login de l'utilisateur.
Groupe principal	guest configure le groupe principal de l'utilisateur.
Groupe additionnel	admin audit authpf bin bind daemon dialer ftp games guest guest Choisir des groupes supplémentaires pour ce compte. Note: Ctrt-dic (ou command-dic sur Mac) pour sélectionner des groupes.
Dossier personnel	Entrer le chemin du répertoire racine pour cet utilisateur. Laisser ce champ vide pour utiliser le chemin par défaut /mnt.
Portail utilisateur	☑ Autorise l'accès au portail utilisateur.
Ajouter Annuler	
	Copyright (© 2012-2014 The NAS4Free Project

5. Vous aurez alors la confirmation que la configuration fut modifiée. **Cliquez** sur **Appliquez les modifications**.



Vous aurez alors la confirmation que les changements ont été enregistrés.

Vous pouvez par la suite accéder au partage de fichiers SMB/CIFS avec la même méthode qu'expliquée dans la section *Création d'un serveur Samba*.

Installation d'une caméra IP

Un réseau se doit d'être sécurisé au niveau virtuel, mais également au niveau physique. Souvent, les équipements réseau sont installés dans une pièce dédiée ou une armoire. Cette pièce se doit d'être sécurisée. Normalement, on instaure un système de contrôle d'accès par carte à puce ou un système biométrique par scanneur rétinien ou par une analyse de la paume de la main ou encore d'une empreinte digitale. Il ne faut cependant pas oublier la surveillance à l'intérieur de la pièce puisque le contrôle d'accès ne surveille pas en temps réel les agissements des employés. Cette surveillance se fait par caméra IP. Cette caméra est souvent reliée à un enregistreur dédié, mais certains autres systèmes peuvent prendre en charge l'enregistrement du flux vidéo, notamment les NAS *Synology* et *QNap*. Une plateforme de moyenne et grande échelle comme *Milestone* est souvent instaurée lorsque l'entreprise dispose de plusieurs dizaines de caméras de surveillance et assure la gestion complète des caméras, des enregistrements et de l'archivage des flux vidéos.

Toutefois, nous n'avions aucune de ces solutions décrites. Nous nous sommes donc contentés d'installer la caméra et de la configurer sur le réseau. Il suffisait de brancher la caméra au commutateur. Celle-ci se voit alors attribuer une adresse IP dynamiquement par le serveur DHCP. Nous nous connectons ensuite à cette caméra via un navigateur web pour avoir accès au flux vidéo.

Toutefois, nous n'avons accès qu'à ce flux puisqu'aucun enregistreur n'est présent sur le réseau, rendant l'intégration de cette caméra IP complètement inutile.

Il serait intéressant dans le futur de mentionner l'existence du programme iSpy Connect (http://www.ispyconnect.com). Ce logiciel très complet de type OpenSource et gratuit permet l'intégration de l'enregistrement de flux vidéos à partir de caméras IP. Il faudrait cependant s'assurer que le modèle de caméra IP dont nous disposons est compatible avec le logiciel. Si les équipements sont compatibles, l'intégration de ce logiciel apporterait un plus à ce projet et rendrait l'installation de la caméra IP utile. Ce n'est qu'à l'écriture de ce rapport que nous avons réalisé à quel point la tâche à effectuer était inutile et nous n'avions malheureusement plus le temps pour tester cette solution logicielle.

Partage d'une connexion Internet

Dans ce projet, nous avions également à faire un partage de connexion Internet entre une machine Windows et une machine Linux.

Comme nous étions dans un environnement virtualisé sous VMware ESXi, la tâche fut légèrement plus complexe à réaliser puisque nous devions passer par des interfaces réseau et des *vSwitch* virtuelles. Toutefois, nous avons été capables d'effectuer ce partage de la manière suivante avec *VMware Workstation* installé sur un Windows Server 2012 R2 physique. Sachez toutefois que ce type de partage de connexion est inutile et excessivement peu utilisé en industrie. On utilisait auparavant un tel partage de connexion pour filtrer celle-ci vers d'autres machines. Désormais, des systèmes de pare-feu tels que pfSense sont beaucoup plus utilisés que ce type de partage pour filtrer une connexion WAN, et la très grande propagation des routeurs sur le marché ont carrément fait disparaître cette manipulation.

- Créer une machine virtuelle Linux avec fun adaptateur réseau de type host only. Cette machine virtuelle sera cliente de la connexion Internet. Avec un adaptateur réseau configuré en mode host only, la machine virtuelle ne pourra communiquer qu'avec l'ordinateur physique, c'est à dire qu'avec Windows Server 2012 R2.
- 2. Terminer l'installation de la distribution Linux.
- 3. Partager la connexion Internet au moyen d'un partage de la carte réseau connectée au WAN.
 - a) Ouvrir les Connexions réseau. Allez dans le **Panneau de configuration**. Sous le Centre Réseau et Partage, cliquez sur **Afficher les connexions réseau**.



b) Cliquez avec le bouton droit sur la connexion que vous souhaitez partager, puis cliquez sur **Propriétés**. Si vous êtes invité à fournir un mot de passe administrateur ou une confirmation, fournissez le mot de passe ou la confirmation.



c) Cliquez sur l'onglet Partage, puis activez la case à cocher Autoriser d'autres utilisateurs du réseau à se connecter via la connexion Internet de cet ordinateur.

🖗 vEthernet (Intel(R) 82574L Gigabit Network C 🗙
Networking Sharing
Internet Connection Sharing ✓ Allow other <u>n</u> etwork users to connect through this computer's Internet connection
Home networking connection:
✓ Allow other network users to control or disable the shared Internet connection
Settings
OK Cancel

Pour plus d'informations sur le partage de connexion Microsoft, visitez le lien suivant : <u>http://windows.microsoft.com/fr-ca/windows/using-internet-connection-sharing#1TC=windows-7</u>

Conclusion

En résumé, ce deuxième projet du cours *Implanter un réseau* a présenté en détail comment ajouter divers services sur un réseau. Nous avons instauré un service Windows Server Update Services ainsi qu'un serveur complet de déploiement et de capture. Nous avons également instauré un serveur DFS ainsi que deux serveurs de partage de fichiers Microsoft pour épauler ce service. La seconde partie de ce rapport s'effectuait sur un système Linux. Nous avons instauré un service Web Apache HTTP, un serveur FTP, ainsi qu'un serveur Samba sur la version gratuite du système d'exploitation Red Hat Enterprise Linux, soit CentOS 6.5. La suite LAMP (*Linux, Apache, MySQL, PHP*) fut installée sur ce système. Un partage de connexion Internet fut également mis en oeuvre. Finalement, l'installation d'une caméra IP fut effectuée, malgré le fait qu'aucun système d'enregistrement vidéo ne fut présenté. Un NAS sous le système FreeBSD NAS4Free constituait la dernière partie de la mise en oeuvre de ce réseau.

Tout comme la première partie du projet, nous avons complètement virtualisé notre environnement de travail. Cette méthode de travail nous a grandement aidés en terme de productivité et de rapidité d'exécution, tout en nous faisant découvrir cette technologie de plus en plus adoptée en industrie. Cela nous a permit non seulement de conserver l'environnement VMware ESXi que nous avons créé de toute pièce lors du premier projet, mais également de conserver toutes les machines virtuelles créer et de contribuer à l'agrandissement du réseau de manière transparente, sans toucher à ces machines et sans en altérer leur fonctionnement. Nous continuons de croire que la virtualisation devrait devenir la fondation même de ce cours puisqu'elle offre non seulement une foule d'avantages pouvant être exploités dans l'industrie, mais ces mêmes avantages peuvent être mis à profit dans le cours afin d'augmenter la productivité des étudiants. De ce fait, nous pourrions voir plus de contenu dans le cours et ainsi bonifier l'apprentissage des futurs étudiants. Nous avons démontré lors de ce projet qu'il est possible d'instaurer la virtualisation avec le matériel fourni. Certes, ce dernier n'est peut-être pas idéal en terme de performance, mais le projet est tout de même très réalisable. Si un budget est mis en oeuvre pour la modernisation du matériel dans le local où ce cours est donné, il serait intéressant d'acheter du matériel compatible avec les hyperviseurs de dernière génération afin que les étudiants puissent bénéficier des apprentissages de la virtualisation dans les meilleures conditions possibles. De plus, ce matériel ne coûte pas beaucoup plus cher que du matériel normal.

Ceci conclut ce rapport. Nous espérons que celui-ci aidera d'éventuels élèves inscrits dans ce cours. Merci de votre lecture.

ierre-Luc Clisle

Pierre-Luc Delisle

Muillaime Madea

Guillaume Nadeau
Annexes

Annexe 1 : smb.conf

#	ТЕХТЕ
1	# This is the main Samba configuration file. You should read the
2	# smb.conf(5) manual page in order to understand the options listed
3	# here. Samba has a huge number of configurable options (perhaps too
4	# many!) most of which are not shown in this example
5	#
6	# For a step to step guide on installing, configuring and using samba,
7	# read the Samba-HOWTO-Collection. This may be obtained from:
8	# http://www.samba.org/samba/docs/Samba-HOWTO-Collection.pdf
9	#
10	# Many working examples of smb.conf files can be found in the
11	# Samba-Guide which is generated daily and can be downloaded from:
12	# http://www.samba.org/samba/docs/Samba-Guide.pdf
13	#
14	# Any line which starts with a ; (semi-colon) or a # (hash)
15	# is a comment and is ignored. In this example we will use a #
16	# for commentry and a ; for parts of the config file that you
17	# may wish to enable
18	#
19	# NOTE: Whenever you modify this file you should run the command "testparm"
20	# to check that you have not made any basic syntactic errors.
21	#
22	#
23	# SELINUX NOTES:
24	#

#	TEXTE
25	# If you want to use the useradd/groupadd family of binaries please run:
26	# setsebool -P samba_domain_controller on
27	#
28	# If you want to share home directories via samba please run:
29	# setsebool -P samba_enable_home_dirs on
30	#
31	# If you create a new directory you want to share you should mark it as
32	# "samba_share_t" so that selinux will let you write into it.
33	# Make sure not to do that on system directories as they may already have
34	# been marked with othe SELinux labels.
35	#
36	# Use Is -IdZ /path to see which context a directory has
37	#
38	# Set labels only on directories you created!
39	# To set a label use the following: chcon -t samba_share_t /path
40	#
41	# If you need to share a system created directory you can use one of the
42	# following (read-only/read-write):
43	# setsebool -P samba_export_all_ro on
44	# or
45	# setsebool -P samba_export_all_rw on
46	#
47	# If you want to run scripts (preexec/root prexec/print command/) please
48	# put them into the /var/lib/samba/scripts directory so that smbd will be
49	# allowed to run them.
50	# Make sure you COPY them and not MOVE them so that the right SELinux context
51	# is applied, to check all is ok use restorecon -R -v /var/lib/samba/scripts
52	#

#	TEXTE
53	#
54	#
55	#=====================================
56	
57	[global]
58	workgroup = workgroup
59	security = share
60	dos charset = CP936
61	server string = Centos
62	server min protocol = SMB2
63	client max protocol = SMB3
64	client min protocol = SMB2
65	
66	# Network Related Options
67	#
68	<pre># workgroup = NT-Domain-Name or Workgroup-Name, eg: MIDEARTH</pre>
69	#
70	<pre># server string is the equivalent of the NT Description field</pre>
71	#
72	<pre># netbios name can be used to specify a server name not tied to the hostname</pre>
73	#
74	<pre># Interfaces lets you configure Samba to use multiple interfaces</pre>
75	# If you have multiple network interfaces then you can list the ones
76	<pre># you want to listen on (never omit localhost)</pre>
77	#
78	# Hosts Allow/Hosts Deny lets you restrict who can connect, and you can
79	<pre># specifiy it as a per share option as well</pre>
80	#

#	TEXTE
81	workgroup = WORKGROUP
82	server string = Samba Server Version %v
83	
84	;netbios name = MYSERVER
85	
86	;interfaces = lo eth0 192.168.12.2/24 192.168.13.2/24
87	;hosts allow = 127. 192.168.12. 192.168.13.
88	
89	# Logging Options
90	#
91	# Log File let you specify where to put logs and how to split them up.
92	#
93	<pre># Max Log Size let you specify the max size log files should reach</pre>
94	
95	<pre># logs split per machine</pre>
96	log file = /var/log/samba/log.%m
97	<pre># max 50KB per log file, then rotate</pre>
98	max log size = 50
99	
100	<pre># Standalone Server Options</pre>
101	#
102	<pre># Scurity can be set to user, share(deprecated) or server(deprecated)</pre>
103	#
104	<pre># Backend to store user information in. New installations should</pre>
105	<pre># use either tdbsam or ldapsam. smbpasswd is available for backwards</pre>
106	<pre># compatibility. tdbsam requires no further configuration.</pre>
107	
108	

#	ТЕХТЕ
109	<pre>security = user</pre>
110	<pre>passdb backend = tdbsam</pre>
111	
112	# Domain Members Options
113	#
114	<pre># Security must be set to domain or ads</pre>
115	#
116	<pre># Use the realm option only with security = ads</pre>
117	# Specifies the Active Directory realm the host is part of
118	#
119	<pre># Backend to store user information in. New installations should</pre>
120	<pre># use either tdbsam or ldapsam. smbpasswd is available for backwards</pre>
121	<pre># compatibility. tdbsam requires no further configuration.</pre>
122	#
123	<pre># Use password server option only with security = server or if you can't</pre>
124	<pre># use the DNS to locate Domain Controllers</pre>
125	<pre># The argument list may include:</pre>
126	<pre># password server = My_PDC_Name [My_BDC_Name] [My_Next_BDC_Name]</pre>
127	<pre># or to auto-locate the domain controller/s</pre>
128	<pre># password server = *</pre>
129	
130	
131	;security = domain
132	;passdb backend = tdbsam
133	;realm = MY_REALM
134	
135	;password server = <nt-server-name></nt-server-name>
136	

#	ТЕХТЕ
137	<pre># Domain Controller Options</pre>
138	#
139	<pre># Security must be set to user for domain controllers</pre>
140	#
141	<pre># Backend to store user information in. New installations should</pre>
142	<pre># use either tdbsam or ldapsam. smbpasswd is available for backwards</pre>
143	<pre># compatibility. tdbsam requires no further configuration.</pre>
144	#
145	# Domain Master specifies Samba to be the Domain Master Browser. This
146	<pre># allows Samba to collate browse lists between subnets. Don't use this</pre>
147	<pre># if you already have a Windows NT domain controller doing this job</pre>
148	#
149	<pre># Domain Logons let Samba be a domain logon server for Windows workstations.</pre>
150	#
151	<pre># Logon Scrpit let yuou specify a script to be run at login time on the client</pre>
152	<pre># You need to provide it in a share called NETLOGON</pre>
153	#
154	<pre># Logon Path let you specify where user profiles are stored (UNC path)</pre>
155	#
156	<pre># Various scripts can be used on a domain controller or stand-alone</pre>
157	<pre># machine to add or delete corresponding unix accounts</pre>
158	#
159	;security = user
160	;passdb backend = tdbsam
161	
162	;domain master = yes
163	;domain logons = yes
164	

#	TEXTE
165	;# the login script name depends on the machine name
166	;logon script = %m.bat
167	;# the login script name depends on the unix user used
168	;logon script = %u.bat
169	;logon path = \\%L\Profiles\%u
170	;# disables profiles support by specifing an empty path
171	;logon path =
172	
173	;add user script = /usr/sbin/useradd "%u" -n -g users
174	;add group script = /usr/sbin/groupadd "%g"
175	;add machine script = /usr/sbin/useradd -n -c "Workstation (%u)" -M -d /nohome -s /bin/false "%u"
176	;delete user script = /usr/sbin/userdel "%u"
177	;delete user from group script = /usr/sbin/userdel "%u" "%g"
178	;delete group script = /usr/sbin/groupdel "%g"
178 179	;delete group script = /usr/sbin/groupdel "%g"
178 179 180	;delete group script = /usr/sbin/groupdel "%g"
178 179 180 181	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options</pre>
178 179 180 181 182	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options #</pre>
178 179 180 181 182 183	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # # set local master to no if you don't want Samba to become a master</pre>
178 179 180 181 182 183 183	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply</pre>
178 179 180 181 182 183 184 185	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply #</pre>
 178 179 180 181 182 183 184 185 186 	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply # # OS Level determines the precedence of this server in master browser</pre>
178 179 180 181 182 183 184 185 186 187	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply # # OS Level determines the precedence of this server in master browser # elections. The default value should be reasonable</pre>
178 179 180 181 182 183 184 185 186 187 188	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply # # OS Level determines the precedence of this server in master browser # elections. The default value should be reasonable #</pre>
178 179 180 181 182 183 184 185 186 187 188 189	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply # # OS Level determines the precedence of this server in master browser # elections. The default value should be reasonable # # Preferred Master causes Samba to force a local browser election on startup</pre>
178 179 180 181 182 183 184 185 186 187 188 189 190	<pre>;delete group script = /usr/sbin/groupdel "%g" # Browser Control Options # # set local master to no if you don't want Samba to become a master # browser on your network. Otherwise the normal election rules apply # # OS Level determines the precedence of this server in master browser # elections. The default value should be reasonable # # Preferred Master causes Samba to force a local browser election on startup # and gives it a slightly higher chance of winning the election</pre>

#	ТЕХТЕ
192	;os level = 33
193	;preferred master = yes
194	
195	# Name Resolution
196	<pre># Windows Internet Name Serving Support Section:</pre>
197	# Note: Samba can be either a WINS Server, or a WINS Client, but NOT both
198	#
199	<pre># - WINS Support: Tells the NMBD component of Samba to enable it's WINS Server</pre>
200	#
201	# – WINS Server: Tells the NMBD components of Samba to be a WINS Client
202	#
203	<pre># - WINS Proxy: Tells Samba to answer name resolution queries on</pre>
204	<pre># behalf of a non WINS capable client, for this to work there must be</pre>
205	# at least one
206	#
207	<pre># DNS Proxy - tells Samba whether or not to try to resolve NetBIOS names</pre>
208	# via DNS nslookups.
209	
210	;wins support = yes
211	;wins server = w.x.y.z
212	;wins proxy = yes
213	
214	;dns proxy = yes
215	
216	<pre># Printing Options</pre>
217	#
218	# Load Printers let you load automatically the list of printers rather
219	<pre># than setting them up individually</pre>

#	ТЕХТЕ
220	#
221	# Cups Options let you pass the cups libs custom options, setting it to raw
222	<pre># for example will let you use drivers on your Windows clients</pre>
223	#
224	<pre># Printcap Name let you specify an alternative printcap file</pre>
225	#
226	# You can choose a non default printing system using the Printing option
227	
228	load printers = yes
229	<pre>cups options = raw</pre>
230	
231	;printcap name = /etc/printcap
232	<pre>#obtain list of printers automatically on SystemV</pre>
233	;printcap name = lpstat
234	;printing = cups
235	
236	<pre># Filesystem Options</pre>
237	#
238	<pre># The following options can be uncommented if the filesystem supports</pre>
239	<pre># Extended Attributes and they are enabled (usually by the mount option</pre>
240	<pre># user_xattr). Thess options will let the admin store the DOS attributes</pre>
241	# in an EA and make samba not mess with the permission bits.
242	#
243	<pre># Note: these options can also be set just per share, setting them in global</pre>
244	# makes them the default for all shares
244 245	# makes them the default for all shares
244 245 246	<pre># makes them the default for all shares ;map archive = no</pre>

#	ТЕХТЕ
248	;map read only = no
249	;map system = no
250	;store dos attributes = yes
251	
252	
253	#=====================================
254	
255	[homes]
256	<pre>comment = Home Directories</pre>
257	browseable = no
258	writable = yes
259	;valid users = %S
260	;valid users = MYDOMAIN\%S
261	
262	[printers]
263	<pre>comment = All Printers</pre>
264	<pre>path = /var/spool/samba</pre>
265	browseable = no
266	guest ok = no
267	writable = no
268	printable = yes
269	
270	# Un-comment the following and create the netlogon directory for Domain Logons
271	;[netlogon]
272	;comment = Network Logon Service
273	;path = /var/lib/samba/netlogon
274	;guest ok = yes
275	;writable = no

#	ТЕХТЕ
276	;share modes = no
277	
278	
279	<pre># Un-comment the following to provide a specific roving profile share</pre>
280	<pre># the default is to use the user's home directory</pre>
281	;[Profiles]
282	<pre>;path = /var/lib/samba/profiles</pre>
283	;browseable = no
284	;guest ok = yes
285	
286	
287	<pre># A publicly accessible directory, but read only, except for people in</pre>
288	# the "staff" group
289	
290	[Public]
291	<pre>comment = Public Stuff</pre>
292	<pre>path = /home/Samba</pre>
293	writable = yes
294	printable = no
295	<pre>write list = +staff</pre>
296	
297	
298	[Share]
299	<pre>path = /samba/shares</pre>
300	browsable = yes
301	writable = yes
302	force group = users
303	create mask = 0660

#	ТЕХТЕ
304	directory mask = 0771
305	

Annexe 2 : httpd.conf

#	ТЕХТЕ
1	#
2	# This is the main Apache server configuration file. It contains the
3	# configuration directives that give the server its instructions.
4	# See <url:http: 2.2="" docs="" httpd.apache.org=""></url:http:> for detailed information.
5	# In particular, see
6	# <url:http: 2.2="" directives.html="" docs="" httpd.apache.org="" mod=""></url:http:>
7	# for a discussion of each configuration directive.
8	#
9	#
10	# Do NOT simply read the instructions in here without understanding
11	# what they do. They're here only as hints or reminders. If you are unsure
12	# consult the online docs. You have been warned.
13	#
14	# The configuration directives are grouped into three basic sections:
15	# 1. Directives that control the operation of the Apache server process as a
16	# whole (the 'global environment').
17	# 2. Directives that define the parameters of the 'main' or 'default' server,
18	# which responds to requests that aren't handled by a virtual host.
19	# These directives also provide default values for the settings
20	# of all virtual hosts.
21	# 3. Settings for virtual hosts, which allow Web requests to be sent to
22	# different IP addresses or hostnames and have them handled by the
23	# same Apache server process.
24	#
25	# Configuration and logfile names: If the filenames you specify for many
26	# of the server's control files begin with "/" (or "drive:/" for Win32), the

#	ТЕХТЕ
27	# server will use that explicit path. If the filenames do *not* begin
28	# with "/", the value of ServerRoot is prepended so "logs/foo.log"
29	# with ServerRoot set to "/etc/httpd" will be interpreted by the
30	# server as "/etc/httpd/logs/foo.log".
31	#
32	
33	### Section 1: Global Environment
34	#
35	# The directives in this section affect the overall operation of Apache,
36	# such as the number of concurrent requests it can handle or where it
37	# can find its configuration files.
38	#
39	
40	#
41	# Don't give away too much information about all the subcomponents
42	# we are running. Comment out this line if you don't mind remote sites
43	# finding out what major optional modules you are running
44	ServerTokens OS
45	
46	#
47	# ServerRoot: The top of the directory tree under which the server's
48	# configuration, error, and log files are kept.
49	#
50	# NOTE! If you intend to place this on an NFS (or otherwise network)
51	# mounted filesystem then please read the LockFile documentation
52	# (available at <url:http: 2.2="" docs="" httpd.apache.org="" mod="" mpm_common.html#lockfile="">);</url:http:>
53	# you will save yourself a lot of trouble.
54	#

#	TEXTE
55	# Do NOT add a slash at the end of the directory path.
56	#
57	ServerRoot "/etc/httpd"
58	
59	#
60	# PidFile: The file in which the server should record its process
61	# identification number when it starts. Note the PIDFILE variable in
62	# /etc/sysconfig/httpd must be set appropriately if this location is
63	# changed.
64	#
65	PidFile run/httpd.pid
66	
67	#
68	# Timeout: The number of seconds before receives and sends time out.
69	#
70	Timeout 60
71	
72	#
73	<pre># KeepAlive: Whether or not to allow persistent connections (more than</pre>
74	<pre># one request per connection). Set to "Off" to deactivate.</pre>
75	#
76	KeepAlive Off
77	
78	#
79	<pre># MaxKeepAliveRequests: The maximum number of requests to allow</pre>
80	<pre># during a persistent connection. Set to 0 to allow an unlimited amount.</pre>
81	# We recommend you leave this number high, for maximum performance.
82	#

#	ТЕХТЕ
83	MaxKeepAliveRequests 100
84	
85	#
86	<pre># KeepAliveTimeout: Number of seconds to wait for the next request from the</pre>
87	<pre># same client on the same connection.</pre>
88	#
89	KeepAliveTimeout 15
90	
91	##
92	<pre>## Server-Pool Size Regulation (MPM specific)</pre>
93	##
94	
95	# prefork MPM
96	<pre># StartServers: number of server processes to start</pre>
97	<pre># MinSpareServers: minimum number of server processes which are kept spare</pre>
98	<pre># MaxSpareServers: maximum number of server processes which are kept spare</pre>
99	<pre># ServerLimit: maximum value for MaxClients for the lifetime of the server</pre>
100	<pre># MaxClients: maximum number of server processes allowed to start</pre>
101	<pre># MaxRequestsPerChild: maximum number of requests a server process serves</pre>
102	<ifmodule prefork.c=""></ifmodule>
103	StartServers 8
104	MinSpareServers 5
105	MaxSpareServers 20
106	ServerLimit 256
107	MaxClients 256
108	MaxRequestsPerChild 4000
109	
110	

#	ТЕХТЕ
111	# worker MPM
112	<pre># StartServers: initial number of server processes to start</pre>
113	<pre># MaxClients: maximum number of simultaneous client connections</pre>
114	<pre># MinSpareThreads: minimum number of worker threads which are kept spare</pre>
115	<pre># MaxSpareThreads: maximum number of worker threads which are kept spare</pre>
116	<pre># ThreadsPerChild: constant number of worker threads in each server process</pre>
117	<pre># MaxRequestsPerChild: maximum number of requests a server process serves</pre>
118	<ifmodule worker.c=""></ifmodule>
119	StartServers 4
120	MaxClients 300
121	MinSpareThreads 25
122	MaxSpareThreads 75
123	ThreadsPerChild 25
124	MaxRequestsPerChild 0
125	
126	
127	#
128	<pre># Listen: Allows you to bind Apache to specific IP addresses and/or</pre>
129	<pre># ports, in addition to the default. See also the <virtualhost></virtualhost></pre>
130	<pre># directive.</pre>
131	#
132	# Change this to Listen on specific IP addresses as shown below to
133	<pre># prevent Apache from glomming onto all bound IP addresses (0.0.0.0)</pre>
134	#
135	#Listen 12.34.56.78:80
136	Listen 80
137	
138	#

#	ТЕХТЕ
139	<pre># Dynamic Shared Object (DSO) Support</pre>
140	#
141	$\ensuremath{\texttt{\#}}$ To be able to use the functionality of a module which was built as a DSO you
142	<pre># have to place corresponding `LoadModule' lines at this location so the</pre>
143	<pre># directives contained in it are actually available _before_ they are used.</pre>
144	<pre># Statically compiled modules (those listed by `httpd $-l'$) do not need</pre>
145	# to be loaded here.
146	#
147	# Example:
148	<pre># LoadModule foo_module modules/mod_foo.so</pre>
149	#
150	LoadModule auth_basic_module modules/mod_auth_basic.so
151	LoadModule auth_digest_module modules/mod_auth_digest.so
152	LoadModule authn_file_module modules/mod_authn_file.so
153	LoadModule authn_alias_module modules/mod_authn_alias.so
154	LoadModule authn_anon_module modules/mod_authn_anon.so
155	LoadModule authn_dbm_module modules/mod_authn_dbm.so
156	LoadModule authn_default_module modules/mod_authn_default.so
157	LoadModule authz_host_module modules/mod_authz_host.so
158	LoadModule authz_user_module modules/mod_authz_user.so
159	LoadModule authz_owner_module modules/mod_authz_owner.so
160	LoadModule authz_groupfile_module modules/mod_authz_groupfile.so
161	LoadModule authz_dbm_module modules/mod_authz_dbm.so
162	LoadModule authz_default_module modules/mod_authz_default.so
163	LoadModule ldap_module modules/mod_ldap.so
164	LoadModule authnz_ldap_module modules/mod_authnz_ldap.so
165	LoadModule include_module modules/mod_include.so
166	LoadModule log_config_module modules/mod_log_config.so

#	TEXTE	
167	LoadModule	logio_module modules/mod_logio.so
168	LoadModule	env_module modules/mod_env.so
169	LoadModule	<pre>ext_filter_module modules/mod_ext_filter.so</pre>
170	LoadModule	<pre>mime_magic_module modules/mod_mime_magic.so</pre>
171	LoadModule	expires_module modules/mod_expires.so
172	LoadModule	<pre>deflate_module modules/mod_deflate.so</pre>
173	LoadModule	headers_module modules/mod_headers.so
174	LoadModule	usertrack_module modules/mod_usertrack.so
175	LoadModule	<pre>setenvif_module modules/mod_setenvif.so</pre>
176	LoadModule	<pre>mime_module modules/mod_mime.so</pre>
177	LoadModule	dav_module modules/mod_dav.so
178	LoadModule	<pre>status_module modules/mod_status.so</pre>
179	LoadModule	<pre>autoindex_module modules/mod_autoindex.so</pre>
180	LoadModule	info_module modules/mod_info.so
181	LoadModule	dav_fs_module modules/mod_dav_fs.so
182	LoadModule	<pre>vhost_alias_module modules/mod_vhost_alias.so</pre>
183	LoadModule	<pre>negotiation_module modules/mod_negotiation.so</pre>
184	LoadModule	dir_module modules/mod_dir.so
185	LoadModule	<pre>actions_module modules/mod_actions.so</pre>
186	LoadModule	<pre>speling_module modules/mod_speling.so</pre>
187	LoadModule	userdir_module modules/mod_userdir.so
188	LoadModule	alias_module modules/mod_alias.so
189	LoadModule	<pre>substitute_module modules/mod_substitute.so</pre>
190	LoadModule	rewrite_module modules/mod_rewrite.so
191	LoadModule	proxy_module modules/mod_proxy.so
192	LoadModule	<pre>proxy_balancer_module modules/mod_proxy_balancer.so</pre>
193	LoadModule	proxy_ftp_module modules/mod_proxy_ftp.so
194	LoadModule	<pre>proxy_http_module modules/mod_proxy_http.so</pre>

#	ТЕХТЕ
195	LoadModule proxy_ajp_module modules/mod_proxy_ajp.so
196	LoadModule proxy_connect_module modules/mod_proxy_connect.so
197	LoadModule cache_module modules/mod_cache.so
198	LoadModule suexec_module modules/mod_suexec.so
199	LoadModule disk_cache_module modules/mod_disk_cache.so
200	LoadModule cgi_module modules/mod_cgi.so
201	LoadModule version_module modules/mod_version.so
202	
203	#
204	# The following modules are not loaded by default:
205	#
206	<pre>#LoadModule asis_module modules/mod_asis.so</pre>
207	<pre>#LoadModule authn_dbd_module modules/mod_authn_dbd.so</pre>
208	<pre>#LoadModule cern_meta_module modules/mod_cern_meta.so</pre>
209	<pre>#LoadModule cgid_module modules/mod_cgid.so</pre>
210	<pre>#LoadModule dbd_module modules/mod_dbd.so</pre>
211	<pre>#LoadModule dumpio_module modules/mod_dumpio.so</pre>
212	<pre>#LoadModule filter_module modules/mod_filter.so</pre>
213	<pre>#LoadModule ident_module modules/mod_ident.so</pre>
214	<pre>#LoadModule log_forensic_module modules/mod_log_forensic.so</pre>
215	<pre>#LoadModule unique_id_module modules/mod_unique_id.so</pre>
216	#
217	
218	#
219	<pre># Load config files from the config directory "/etc/httpd/conf.d".</pre>
220	#
221	<pre>Include conf.d/*.conf</pre>
222	

#	ТЕХТЕ
223	#
224	<pre># ExtendedStatus controls whether Apache will generate "full" status</pre>
225	<pre># information (ExtendedStatus On) or just basic information (ExtendedStatus</pre>
226	# Off) when the "server-status" handler is called. The default is Off.
227	#
228	#ExtendedStatus On
229	
230	#
231	# If you wish httpd to run as a different user or group, you must run
232	<pre># httpd as root initially and it will switch.</pre>
233	#
234	# User/Group: The name (or #number) of the user/group to run httpd as.
235	<pre># . On SCO (ODT 3) use "User nouser" and "Group nogroup".</pre>
236	$\ensuremath{\#}$. On HPUX you may not be able to use shared memory as nobody, and the
237	<pre># suggested workaround is to create a user www and use that user.</pre>
238	<pre># NOTE that some kernels refuse to setgid(Group) or semctl(IPC_SET)</pre>
239	<pre># when the value of (unsigned)Group is above 60000;</pre>
240	<pre># don't use Group #-1 on these systems!</pre>
241	#
242	User apache
243	Group apache
244	
245	<pre>### Section 2: 'Main' server configuration</pre>
246	#
247	# The directives in this section set up the values used by the 'main'
248	<pre># server, which responds to any requests that aren't handled by a</pre>
249	<pre># <virtualhost> definition. These values also provide defaults for</virtualhost></pre>
250	<pre># any <virtualhost> containers you may define later in the file.</virtualhost></pre>

#	ТЕХТЕ
251	#
252	<pre># All of these directives may appear inside <virtualhost> containers,</virtualhost></pre>
253	<pre># in which case these default settings will be overridden for the</pre>
254	<pre># virtual host being defined.</pre>
255	#
256	
257	#
258	# ServerAdmin: Your address, where problems with the server should be
259	<pre># e-mailed. This address appears on some server-generated pages, such</pre>
260	<pre># as error documents. e.g. admin@your-domain.com</pre>
261	#
262	ServerAdmin root@localhost
263	
264	#
265	<pre># ServerName gives the name and port that the server uses to identify itself.</pre>
266	# This can often be determined automatically, but we recommend you specify
267	<pre># it explicitly to prevent problems during startup.</pre>
268	#
269	# If this is not set to valid DNS name for your host, server-generated
270	<pre># redirections will not work. See also the UseCanonicalName directive.</pre>
271	#
272	<pre># If your host doesn't have a registered DNS name, enter its IP address here.</pre>
273	# You will have to access it by its address anyway, and this will make
274	<pre># redirections work in a sensible way.</pre>
275	#
276	<pre>#ServerName www.example.com:80</pre>
277	
278	#

#	ТЕХТЕ
279	<pre># UseCanonicalName: Determines how Apache constructs self-referencing</pre>
280	<pre># URLs and the SERVER_NAME and SERVER_PORT variables.</pre>
281	# When set "Off", Apache will use the Hostname and Port supplied
282	# by the client. When set "On", Apache will use the value of the
283	<pre># ServerName directive.</pre>
284	#
285	UseCanonicalName Off
286	
287	#
288	<pre># DocumentRoot: The directory out of which you will serve your</pre>
289	<pre># documents. By default, all requests are taken from this directory, but</pre>
290	<pre># symbolic links and aliases may be used to point to other locations.</pre>
291	#
292	DocumentRoot "/var/www/html"
293	
294	#
295	# Each directory to which Apache has access can be configured with respect
296	<pre># to which services and features are allowed and/or disabled in that</pre>
297	<pre># directory (and its subdirectories).</pre>
298	#
299	# First, we configure the "default" to be a very restrictive set of
300	# features.
301	#
302	<directory></directory>
303	Options FollowSymLinks
304	AllowOverride None
305	

#	ТЕХТЕ
307	#
308	<pre># Note that from this point forward you must specifically allow</pre>
309	<pre># particular features to be enabled - so if something's not working as</pre>
310	<pre># you might expect, make sure that you have specifically enabled it</pre>
311	# below.
312	#
313	
314	#
315	# This should be changed to whatever you set DocumentRoot to.
316	#
317	<directory "="" html"="" var="" www=""></directory>
318	
319	#
320	<pre># Possible values for the Options directive are "None", "All",</pre>
321	<pre># or any combination of:</pre>
322	<pre># Indexes Includes FollowSymLinks SymLinksifOwnerMatch ExecCGI MultiViews</pre>
323	#
324	<pre># Note that "MultiViews" must be named *explicitly* "Options All"</pre>
325	# doesn't give it to you.
326	#
327	<pre># The Options directive is both complicated and important. Please see</pre>
328	<pre># http://httpd.apache.org/docs/2.2/mod/core.html#options</pre>
329	# for more information.
330	#
331	Options Indexes FollowSymLinks
332	
333	#
334	<pre># AllowOverride controls what directives may be placed in .htaccess files.</pre>

#	TEXTE
335	<pre># It can be "All", "None", or any combination of the keywords:</pre>
336	<pre># Options FileInfo AuthConfig Limit</pre>
337	#
338	AllowOverride None
339	
340	#
341	<pre># Controls who can get stuff from this server.</pre>
342	#
343	Order allow, deny
344	Allow from all
345	
346	
347	
348	#
349	# UserDir: The name of the directory that is appended onto a user's home
350	<pre># directory if a ~user request is received.</pre>
351	#
352	<pre># The path to the end user account 'public_html' directory must be</pre>
353	# accessible to the webserver userid. This usually means that \sim userid
354	<pre># must have permissions of 711, ~userid/public_html must have permissions</pre>
355	# of 755, and documents contained therein must be world-readable.
356	# Otherwise, the client will only receive a "403 Forbidden" message.
357	#
358	<pre># See also: http://httpd.apache.org/docs/misc/FAQ.html#forbidden</pre>
359	#
360	<ifmodule mod_userdir.c=""></ifmodule>
361	#
362	# UserDir is disabled by default since it can confirm the presence

#	TEXTE
363	<pre># of a username on the system (depending on home directory</pre>
364	<pre># permissions).</pre>
365	#
366	UserDir disabled
367	
368	#
369	<pre># To enable requests to /~user/ to serve the user's public_html</pre>
370	<pre># directory, remove the "UserDir disabled" line above, and uncomment</pre>
371	<pre># the following line instead:</pre>
372	#
373	#UserDir public_html
374	
375	
376	
377	#
378	<pre># Control access to UserDir directories. The following is an example</pre>
379	<pre># for a site where these directories are restricted to read-only.</pre>
380	#
381	<pre>#<directory *="" home="" public_html=""></directory></pre>
382	<pre># AllowOverride FileInfo AuthConfig Limit</pre>
383	<pre># Options MultiViews Indexes SymLinksIfOwnerMatch IncludesNoExec</pre>
384	<pre># <limit get="" options="" post=""></limit></pre>
385	# Order allow, deny
386	# Allow from all
387	#
388	<pre># <limitexcept get="" options="" post=""></limitexcept></pre>
389	# Order deny,allow
390	# Deny from all

#	ТЕХТЕ
391	<pre># </pre>
392	#
393	
394	#
395	<pre># DirectoryIndex: sets the file that Apache will serve if a directory</pre>
396	<pre># is requested.</pre>
397	#
398	<pre># The index.html.var file (a type-map) is used to deliver content-</pre>
399	<pre># negotiated documents. The MultiViews Option can be used for the</pre>
400	<pre># same purpose, but it is much slower.</pre>
401	#
402	DirectoryIndex index.html index.html.var
403	
404	#
405	<pre># AccessFileName: The name of the file to look for in each directory</pre>
406	<pre># for additional configuration directives. See also the AllowOverride</pre>
407	# directive.
408	#
409	AccessFileName .htaccess
410	
411	#
412	<pre># The following lines prevent .htaccess and .htpasswd files from being</pre>
413	# viewed by Web clients.
414	#
415	<files "^\.ht"="" ~=""></files>
416	Order allow, deny
417	Deny from all
418	Satisfy All

#	ТЕХТЕ
419	
420	
421	#
422	<pre># TypesConfig describes where the mime.types file (or equivalent) is</pre>
423	# to be found.
424	#
425	TypesConfig /etc/mime.types
426	
427	#
428	<pre># DefaultType is the default MIME type the server will use for a document</pre>
429	<pre># if it cannot otherwise determine one, such as from filename extensions.</pre>
430	<pre># If your server contains mostly text or HTML documents, "text/plain" is</pre>
431	<pre># a good value. If most of your content is binary, such as applications</pre>
432	<pre># or images, you may want to use "application/octet-stream" instead to</pre>
433	<pre># keep browsers from trying to display binary files as though they are</pre>
434	# text.
435	#
436	DefaultType text/plain
437	
438	#
439	<pre># The mod_mime_magic module allows the server to use various hints from the</pre>
440	<pre># contents of the file itself to determine its type. The MIMEMagicFile</pre>
441	<pre># directive tells the module where the hint definitions are located.</pre>
442	#
443	<ifmodule mod_mime_magic.c=""></ifmodule>
444	<pre># MIMEMagicFile /usr/share/magic.mime</pre>
445	MIMEMagicFile conf/magic
446	

#	ТЕХТЕ
447	
448	#
449	<pre># HostnameLookups: Log the names of clients or just their IP addresses</pre>
450	# e.g., www.apache.org (on) or 204.62.129.132 (off).
451	<pre># The default is off because it'd be overall better for the net if people</pre>
452	<pre># had to knowingly turn this feature on, since enabling it means that</pre>
453	<pre># each client request will result in AT LEAST one lookup request to the</pre>
454	# nameserver.
455	#
456	HostnameLookups Off
457	
458	#
459	<pre># EnableMMAP: Control whether memory-mapping is used to deliver</pre>
460	<pre># files (assuming that the underlying OS supports it).</pre>
461	<pre># The default is on; turn this off if you serve from NFS-mounted</pre>
462	<pre># filesystems. On some systems, turning it off (regardless of</pre>
463	<pre># filesystem) can improve performance; for details, please see</pre>
464	<pre># http://httpd.apache.org/docs/2.2/mod/core.html#enablemmap</pre>
465	#
466	#EnableMMAP off
467	
468	#
469	<pre># EnableSendfile: Control whether the sendfile kernel support is</pre>
470	<pre># used to deliver files (assuming that the OS supports it).</pre>
471	# The default is on; turn this off if you serve from NFS-mounted
472	<pre># filesystems. Please see</pre>
473	<pre># http://httpd.apache.org/docs/2.2/mod/core.html#enablesendfile</pre>
474	#

#	ТЕХТЕ
475	#EnableSendfile off
476	
477	#
478	# ErrorLog: The location of the error log file.
479	<pre># If you do not specify an ErrorLog directive within a <virtualhost></virtualhost></pre>
480	# container, error messages relating to that virtual host will be
481	<pre># logged here. If you *do* define an error logfile for a <virtualhost></virtualhost></pre>
482	<pre># container, that host's errors will be logged there and not here.</pre>
483	#
484	ErrorLog logs/error_log
485	
486	#
487	<pre># LogLevel: Control the number of messages logged to the error_log.</pre>
488	<pre># Possible values include: debug, info, notice, warn, error, crit,</pre>
489	# alert, emerg.
490	#
491	LogLevel warn
492	
493	#
494	# The following directives define some format nicknames for use with
495	<pre># a CustomLog directive (see below).</pre>
496	#
497	LogFormat "%h %l %u %t \"%r\" %>s %b \"%{Referer}i\" \"%{User-Agent}i\"" combined
498	LogFormat "%h %l %u %t \"%r\" %>s %b" common
499	LogFormat "%{Referer}i -> %U" referer
500	LogFormat "%{User-agent}i" agent
501	

#	TEXTE
502	# "combinedio" includes actual counts of actual bytes received (%I) and sent (%0); this
503	<pre># requires the mod_logio module to be loaded.</pre>
504	#LogFormat "%h %l %u %t \"%r\" %>s %b \"%{Referer}i\" \"%{User-Agent}i\" %I %O" combinedio
505	
506	#
507	# The location and format of the access logfile (Common Logfile Format).
508	<pre># If you do not define any access logfiles within a <virtualhost></virtualhost></pre>
509	<pre># container, they will be logged here. Contrariwise, if you *do*</pre>
510	<pre># define per-<virtualhost> access logfiles, transactions will be</virtualhost></pre>
511	<pre># logged therein and *not* in this file.</pre>
512	#
513	#CustomLog logs/access_log common
514	
515	#
516	# If you would like to have separate agent and referer logfiles, uncomment
517	<pre># the following directives.</pre>
518	#
519	#CustomLog logs/referer_log referer
520	<pre>#CustomLog logs/agent_log agent</pre>
521	
522	#
523	# For a single logfile with access, agent, and referer information
524	<pre># (Combined Logfile Format), use the following directive:</pre>
525	#
526	CustomLog logs/access_log combined
527	
528	#

#	ТЕХТЕ
529	<pre># Optionally add a line containing the server version and virtual host</pre>
530	<pre># name to server-generated pages (internal error documents, FTP directory</pre>
531	<pre># listings, mod_status and mod_info output etc., but not CGI generated</pre>
532	<pre># documents or custom error documents).</pre>
533	# Set to "EMail" to also include a mailto: link to the ServerAdmin.
534	<pre># Set to one of: On Off EMail</pre>
535	#
536	ServerSignature On
537	
538	#
539	# Aliases: Add here as many aliases as you need (with no limit). The format is
540	# Alias fakename realname
54 1	#
542	<pre># Note that if you include a trailing / on fakename then the server will</pre>
543	<pre># require it to be present in the URL. So "/icons" isn't aliased in this</pre>
544	<pre># example, only "/icons/". If the fakename is slash-terminated, then the</pre>
545	<pre># realname must also be slash terminated, and if the fakename omits the</pre>
546	# trailing slash, the realname must also omit it.
547	#
548	# We include the /icons/ alias for FancyIndexed directory listings. If you
549	<pre># do not use FancyIndexing, you may comment this out.</pre>
550	#
551	Alias /icons/ "/var/www/icons/"
552	
553	<directory "="" icons"="" var="" www=""></directory>
554	Options Indexes MultiViews FollowSymLinks
555	AllowOverride None
556	Order allow, deny

#	ТЕХТЕ
557	Allow from all
558	
559	
560	#
561	<pre># WebDAV module configuration section.</pre>
562	#
563	<ifmodule mod_dav_fs.c=""></ifmodule>
564	# Location of the WebDAV lock database.
565	DAVLockDB /var/lib/dav/lockdb
566	
567	
568	#
569	<pre># ScriptAlias: This controls which directories contain server scripts.</pre>
570	<pre># ScriptAliases are essentially the same as Aliases, except that</pre>
571	<pre># documents in the realname directory are treated as applications and</pre>
572	# run by the server when requested rather than as documents sent to the client.
573	<pre># The same rules about trailing "/" apply to ScriptAlias directives as to</pre>
574	# Alias.
575	#
576	<pre>ScriptAlias /cgi-bin/ "/var/www/cgi-bin/"</pre>
577	
578	#
579	<pre># "/var/www/cgi-bin" should be changed to whatever your ScriptAliased</pre>
580	# CGI directory exists, if you have that configured.
581	#
582	<directory "="" cgi-bin"="" var="" www=""></directory>
583	AllowOverride None
584	Options None

#	ТЕХТЕ
585	Order allow,deny
586	Allow from all
587	
588	
589	#
590	<pre># Redirect allows you to tell clients about documents which used to exist in</pre>
591	# your server's namespace, but do not anymore. This allows you to tell the
592	<pre># clients where to look for the relocated document.</pre>
593	# Example:
594	<pre># Redirect permanent /foo http://www.example.com/bar</pre>
595	
596	#
597	<pre># Directives controlling the display of server-generated directory listings.</pre>
598	#
599	
600	#
601	<pre># IndexOptions: Controls the appearance of server-generated directory</pre>
602	# listings.
603	#
604	<pre>IndexOptions FancyIndexing VersionSort NameWidth=* HTMLTable Charset=UTF-8</pre>
605	
606	#
607	<pre># AddIcon* directives tell the server which icon to show for different</pre>
608	<pre># files or filename extensions. These are only displayed for</pre>
609	<pre># FancyIndexed directories.</pre>
610	#
611	AddIconByEncoding (CMP,/icons/compressed.gif) x-compress x-gzip
612	

#	ТЕХТЕ
613	AddIconByType (TXT,/icons/text.gif) text/*
614	AddIconByType (IMG,/icons/image2.gif) image/*
615	AddIconByType (SND,/icons/sound2.gif) audio/*
616	AddIconByType (VID,/icons/movie.gif) video/*
617	
618	AddIcon /icons/binary.gif .bin .exe
619	AddIcon /icons/binhex.gif .hqx
620	AddIcon /icons/tar.gif .tar
621	AddIcon /icons/world2.gif .wrl .wrl.gz .vrml .vrm .iv
622	AddIcon /icons/compressed.gif .Z .z .tgz .gz .zip
623	AddIcon /icons/a.gif .ps .ai .eps
624	AddIcon /icons/layout.gif .html .shtml .htm .pdf
625	AddIcon /icons/text.gif .txt
626	AddIcon /icons/c.gif .c
627	AddIcon /icons/p.gif .pl .py
628	AddIcon /icons/f.gif .for
629	AddIcon /icons/dvi.gif .dvi
630	AddIcon /icons/uuencoded.gif .uu
631	AddIcon /icons/script.gif .conf .sh .shar .csh .ksh .tcl
632	AddIcon /icons/tex.gif .tex
633	AddIcon /icons/bomb.gif core
634	
635	AddIcon /icons/back.gif
636	AddIcon /icons/hand.right.gif README
637	AddIcon /icons/folder.gif ^^DIRECTORY^^
638	AddIcon /icons/blank.gif ^^BLANKICON^^
639	
640	#

#	TEXTE
641	<pre># DefaultIcon is which icon to show for files which do not have an icon</pre>
642	<pre># explicitly set.</pre>
643	#
644	<pre>DefaultIcon /icons/unknown.gif</pre>
645	
646	#
647	<pre># AddDescription allows you to place a short description after a file in</pre>
648	<pre># server-generated indexes. These are only displayed for FancyIndexed</pre>
649	# directories.
650	<pre># Format: AddDescription "description" filename</pre>
651	#
652	#AddDescription "GZIP compressed document" .gz
653	#AddDescription "tar archive" .tar
654	#AddDescription "GZIP compressed tar archive" .tgz
655	
656	#
657	$\ensuremath{\texttt{\#}}$ ReadmeName is the name of the README file the server will look for by
658	<pre># default, and append to directory listings.</pre>
659	#
660	<pre># HeaderName is the name of a file which should be prepended to</pre>
661	<pre># directory indexes.</pre>
662	ReadmeName README.html
663	HeaderName HEADER.html
664	
665	#
666	<pre># IndexIgnore is a set of filenames which directory indexing should ignore</pre>
667	<pre># and not include in the listing. Shell-style wildcarding is permitted.</pre>
668	#
#	TEXTE
-----	--
669	<pre>IndexIgnore .??* *~ *# HEADER* README* RCS CVS *,v *,t</pre>
670	
671	#
672	<pre># DefaultLanguage and AddLanguage allows you to specify the language of</pre>
673	# a document. You can then use content negotiation to give a browser a
674	# file in a language the user can understand.
675	#
676	# Specify a default language. This means that all data
677	<pre># going out without a specific language tag (see below) will</pre>
678	# be marked with this one. You probably do NOT want to set
679	# this unless you are sure it is correct for all cases.
680	#
681	<pre># * It is generally better to not mark a page as</pre>
682	# $*$ being a certain language than marking it with the wrong
683	# * language!
684	#
685	# DefaultLanguage nl
686	#
687	# Note 1: The suffix does not have to be the same as the language
688	<pre># keyword those with documents in Polish (whose net-standard</pre>
689	<pre># language code is pl) may wish to use "AddLanguage pl .po" to</pre>
690	<pre># avoid the ambiguity with the common suffix for perl scripts.</pre>
691	#
692	<pre># Note 2: The example entries below illustrate that in some cases</pre>
693	<pre># the two character 'Language' abbreviation is not identical to</pre>
694	<pre># the two character 'Country' code for its country,</pre>
695	<pre># E.g. 'Danmark/dk' versus 'Danish/da'.</pre>
696	#

#	TEXTE
697	# Note 3: In the case of 'ltz' we violate the RFC by using a three char
698	<pre># specifier. There is 'work in progress' to fix this and get</pre>
699	# the reference data for rfc1766 cleaned up.
700	#
701	# Catalan (ca) – Croatian (hr) – Czech (cs) – Danish (da) – Dutch (nl)
702	<pre># English (en) - Esperanto (eo) - Estonian (et) - French (fr) - German (de)</pre>
703	# Greek-Modern (el) - Hebrew (he) - Italian (it) - Japanese (ja)
704	# Korean (ko) – Luxembourgeois∗ (ltz) – Norwegian Nynorsk (nn)
705	# Norwegian (no) – Polish (pl) – Portugese (pt)
706	<pre># Brazilian Portuguese (pt-BR) - Russian (ru) - Swedish (sv)</pre>
707	<pre># Simplified Chinese (zh-CN) - Spanish (es) - Traditional Chinese (zh-TW)</pre>
708	#
709	AddLanguage ca .ca
710	AddLanguage cs .cz .cs
711	AddLanguage da .dk
712	AddLanguage de .de
713	AddLanguage el .el
714	AddLanguage en .en
715	AddLanguage eo .eo
716	AddLanguage es .es
717	AddLanguage et .et
718	AddLanguage fr .fr
719	AddLanguage he .he
720	AddLanguage hr .hr
721	AddLanguage it .it
722	AddLanguage ja .ja
723	AddLanguage ko .ko
724	AddLanguage ltz .ltz

#	ТЕХТЕ
725	AddLanguage nl .nl
726	AddLanguage nn .nn
727	AddLanguage no .no
728	AddLanguage pl .po
729	AddLanguage pt .pt
730	AddLanguage pt-BR .pt-br
731	AddLanguage ru .ru
732	AddLanguage sv .sv
733	AddLanguage zh-CN .zh-cn
734	AddLanguage zh-TW .zh-tw
735	
736	#
737	<pre># LanguagePriority allows you to give precedence to some languages</pre>
738	<pre># in case of a tie during content negotiation.</pre>
739	#
740	# Just list the languages in decreasing order of preference. We have
741	<pre># more or less alphabetized them here. You probably want to change this.</pre>
742	#
743	LanguagePriority en ca cs da de el eo es et fr he hr it ja ko ltz nl nn no pl pt pt-BR ru sv zh-CN zh-TW
744	
745	#
746	<pre># ForceLanguagePriority allows you to serve a result page rather than</pre>
747	<pre># MULTIPLE CHOICES (Prefer) [in case of a tie] or NOT ACCEPTABLE (Fallback)</pre>
748	<pre># [in case no accepted languages matched the available variants]</pre>
749	#
750	ForceLanguagePriority Prefer Fallback
751	
752	#

#	ТЕХТЕ
753	<pre># Specify a default charset for all content served; this enables</pre>
754	<pre># interpretation of all content as UTF-8 by default. To use the</pre>
755	<pre># default browser choice (ISO-8859-1), or to allow the META tags</pre>
756	<pre># in HTML content to override this choice, comment out this</pre>
757	<pre># directive:</pre>
758	#
759	AddDefaultCharset UTF-8
760	
761	#
762	<pre># AddType allows you to add to or override the MIME configuration</pre>
763	<pre># file mime.types for specific file types.</pre>
764	#
765	#AddType application/x-tar .tgz
766	
767	#
768	<pre># AddEncoding allows you to have certain browsers uncompress</pre>
769	<pre># information on the fly. Note: Not all browsers support this.</pre>
770	# Despite the name similarity, the following $\operatorname{Add} *$ directives have nothing
771	<pre># to do with the FancyIndexing customization directives above.</pre>
772	#
773	#AddEncoding x-compress .Z
774	#AddEncoding x-gzip .gz .tgz
775	
776	<pre># If the AddEncoding directives above are commented-out, then you</pre>
777	<pre># probably should define those extensions to indicate media types:</pre>
778	#
779	AddType application/x-compress .Z
780	AddType application/x-gzip .gz .tgz

#	ТЕХТЕ
781	
782	#
783	<pre># MIME-types for downloading Certificates and CRLs</pre>
784	#
785	AddType application/x-x509-ca-cert .crt
786	AddType application/x-pkcs7-crl .crl
787	
788	#
789	<pre># AddHandler allows you to map certain file extensions to "handlers":</pre>
790	<pre># actions unrelated to filetype. These can be either built into the server</pre>
791	<pre># or added with the Action directive (see below)</pre>
792	#
793	<pre># To use CGI scripts outside of ScriptAliased directories:</pre>
794	<pre># (You will also need to add "ExecCGI" to the "Options" directive.)</pre>
795	#
796	#AddHandler cgi-script .cgi
797	
798	#
799	<pre># For files that include their own HTTP headers:</pre>
800	#
801	#AddHandler send-as-is asis
802	
803	#
804	<pre># For type maps (negotiated resources):</pre>
805	# (This is enabled by default to allow the Apache "It Worked" page
806	<pre># to be distributed in multiple languages.)</pre>
807	#
808	AddHandler type-map var

#	ТЕХТЕ
809	
810	#
811	# Filters allow you to process content before it is sent to the client.
812	#
813	<pre># To parse .shtml files for server-side includes (SSI):</pre>
814	<pre># (You will also need to add "Includes" to the "Options" directive.)</pre>
815	#
816	AddType text/html .shtml
817	AddOutputFilter INCLUDES .shtml
818	
819	#
820	# Action lets you define media types that will execute a script whenever
821	# a matching file is called. This eliminates the need for repeated URL
822	<pre># pathnames for oft-used CGI file processors.</pre>
823	<pre># Format: Action media/type /cgi-script/location</pre>
824	<pre># Format: Action handler-name /cgi-script/location</pre>
825	#
826	
827	#
828	<pre># Customizable error responses come in three flavors:</pre>
829	<pre># 1) plain text 2) local redirects 3) external redirects</pre>
830	#
831	<pre># Some examples:</pre>
832	#ErrorDocument 500 "The server made a boo boo."
833	<pre>#ErrorDocument 404 /missing.html</pre>
834	<pre>#ErrorDocument 404 "/cgi-bin/missing_handler.pl"</pre>
835	<pre>#ErrorDocument 402 http://www.example.com/subscription_info.html</pre>
836	#

#	ТЕХТЕ
837	
838	#
839	# Putting this all together, we can internationalize error responses.
840	#
841	<pre># We use Alias to redirect any /error/HTTP_<error>.html.var response to</error></pre>
842	<pre># our collection of by-error message multi-language collections. We use</pre>
843	<pre># includes to substitute the appropriate text.</pre>
844	#
845	# You can modify the messages' appearance without changing any of the
846	<pre># default HTTP_<error>.html.var files by adding the line:</error></pre>
847	#
848	<pre># Alias /error/include/ "/your/include/path/"</pre>
849	#
850	# which allows you to create your own set of files by starting with the
851	<pre># /var/www/error/include/ files and</pre>
852	<pre># copying them to /your/include/path/, even on a per-VirtualHost basis.</pre>
853	#
854	
855	Alias /error/ "/var/www/error/"
856	
857	<ifmodule mod_negotiation.c=""></ifmodule>
858	<ifmodule mod_include.c=""></ifmodule>
859	<directory "="" error"="" var="" www=""></directory>
860	AllowOverride None
861	Options IncludesNoExec
862	AddOutputFilter Includes html
863	AddHandler type-map var
864	Order allow, deny

#	ТЕХТЕ
865	Allow from all
866	LanguagePriority en es de fr
867	ForceLanguagePriority Prefer Fallback
868	
869	
870	<pre># ErrorDocument 400 /error/HTTP_BAD_REQUEST.html.var</pre>
871	<pre># ErrorDocument 401 /error/HTTP_UNAUTHORIZED.html.var</pre>
872	<pre># ErrorDocument 403 /error/HTTP_FORBIDDEN.html.var</pre>
873	<pre># ErrorDocument 404 /error/HTTP_NOT_FOUND.html.var</pre>
874	<pre># ErrorDocument 405 /error/HTTP_METHOD_NOT_ALLOWED.html.var</pre>
875	<pre># ErrorDocument 408 /error/HTTP_REQUEST_TIME_OUT.html.var</pre>
876	<pre># ErrorDocument 410 /error/HTTP_GONE.html.var</pre>
877	<pre># ErrorDocument 411 /error/HTTP_LENGTH_REQUIRED.html.var</pre>
878	<pre># ErrorDocument 412 /error/HTTP_PRECONDITION_FAILED.html.var</pre>
879	<pre># ErrorDocument 413 /error/HTTP_REQUEST_ENTITY_T00_LARGE.html.var</pre>
880	<pre># ErrorDocument 414 /error/HTTP_REQUEST_URI_T00_LARGE.html.var</pre>
881	<pre># ErrorDocument 415 /error/HTTP_UNSUPPORTED_MEDIA_TYPE.html.var</pre>
882	<pre># ErrorDocument 500 /error/HTTP_INTERNAL_SERVER_ERROR.html.var</pre>
883	<pre># ErrorDocument 501 /error/HTTP_NOT_IMPLEMENTED.html.var</pre>
884	<pre># ErrorDocument 502 /error/HTTP_BAD_GATEWAY.html.var</pre>
885	<pre># ErrorDocument 503 /error/HTTP_SERVICE_UNAVAILABLE.html.var</pre>
886	<pre># ErrorDocument 506 /error/HTTP_VARIANT_ALSO_VARIES.html.var</pre>
887	
888	
889	
890	
891	#
892	# The following directives modify normal HTTP response behavior to

#	TEXTE
893	<pre># handle known problems with browser implementations.</pre>
894	#
895	BrowserMatch "Mozilla/2" nokeepalive
896	BrowserMatch "MSIE 4\.0b2;" nokeepalive downgrade-1.0 force-response-1.0
897	BrowserMatch "RealPlayer 4\.0" force-response-1.0
898	BrowserMatch "Java/1\.0" force-response-1.0
899	BrowserMatch "JDK/1\.0" force-response-1.0
900	#
901	<pre># The following directive disables redirects on non-GET requests for</pre>
902	<pre># a directory that does not include the trailing slash. This fixes a</pre>
903	<pre># problem with Microsoft WebFolders which does not appropriately handle</pre>
904	<pre># redirects for folders with DAV methods.</pre>
905	<pre># Same deal with Apple's DAV filesystem and Gnome VFS support for DAV.</pre>
906	#
907	BrowserMatch "Microsoft Data Access Internet Publishing Provider" redirect- carefully
908	BrowserMatch "MS FrontPage" redirect-carefully
909	BrowserMatch "^WebDrive" redirect-carefully
910	BrowserMatch "^WebDAVFS/1.[0123]" redirect-carefully
911	BrowserMatch "^gnome-vfs/1.0" redirect-carefully
912	BrowserMatch "^XML Spy" redirect-carefully
913	BrowserMatch "^Dreamweaver-WebDAV-SCM1" redirect-carefully
914	#
915	<pre># Allow server status reports generated by mod_status,</pre>
916	<pre># with the URL of http://servername/server-status</pre>
917	<pre># Change the ".example.com" to match your domain to enable.</pre>
918	#
919	<pre>#<location server-status=""></location></pre>
920	<pre># SetHandler server-status</pre>

#	ТЕХТЕ
921	# Order deny,allow
922	# Deny from all
923	<pre># Allow from .example.com</pre>
924	#
925	#
926	# Allow remote server configuration reports, with the URL of
927	<pre># http://servername/server-info (requires that mod_info.c be loaded).</pre>
928	<pre># Change the ".example.com" to match your domain to enable.</pre>
929	#
930	<pre>#<location server-info=""></location></pre>
931	<pre># SetHandler server-info</pre>
932	# Order deny,allow
933	# Deny from all
934	<pre># Allow from .example.com</pre>
935	#
936	#
937	<pre># Proxy Server directives. Uncomment the following lines to</pre>
938	<pre># enable the proxy server:</pre>
939	#
940	<pre>#<ifmodule mod_proxy.c=""></ifmodule></pre>
941	#ProxyRequests On
942	#
943	# <proxy *=""></proxy>
944	# Order deny,allow
945	# Deny from all
946	<pre># Allow from .example.com</pre>
947	#
948	#

#	ТЕХТЕ
949	<pre># Enable/disable the handling of HTTP/1.1 "Via:" headers.</pre>
950	<pre># ("Full" adds the server version; "Block" removes all outgoing Via: headers)</pre>
951	<pre># Set to one of: Off On Full Block</pre>
952	#
953	#ProxyVia On
954	#
955	# To enable a cache of proxied content, uncomment the following lines.
956	<pre># See http://httpd.apache.org/docs/2.2/mod/mod_cache.html for more details.</pre>
957	#
958	<pre>#<ifmodule mod_disk_cache.c=""></ifmodule></pre>
959	<pre># CacheEnable disk /</pre>
960	<pre># CacheRoot "/var/cache/mod_proxy"</pre>
961	#
962	#
963	#
964	# End of proxy directives.
965	<pre>### Section 3: Virtual Hosts</pre>
966	#
967	<pre># VirtualHost: If you want to maintain multiple domains/hostnames on your</pre>
968	<pre># machine you can setup VirtualHost containers for them. Most configurations</pre>
969	<pre># use only name-based virtual hosts so the server doesn't need to worry about</pre>
970	# IP addresses. This is indicated by the asterisks in the directives below.
971	#
972	<pre># Please see the documentation at</pre>
973	<pre># <url:http: 2.2="" docs="" httpd.apache.org="" vhosts=""></url:http:></pre>
974	<pre># for further details before you try to setup virtual hosts.</pre>
975	#
976	# You may use the command line option '-S' to verify your virtual host

#	ТЕХТЕ
977	# configuration.
978	#
979	<pre># Use name-based virtual hosting.</pre>
980	#
981	<pre>#NameVirtualHost *:80</pre>
982	#
983	<pre># NOTE: NameVirtualHost cannot be used without a port specifier</pre>
984	<pre># (e.g. :80) if mod_ssl is being used, due to the nature of the</pre>
985	# SSL protocol.
986	<pre># VirtualHost example:</pre>
987	# Almost any Apache directive may go into a VirtualHost container.
988	<pre># The first VirtualHost section is used for requests without a known</pre>
989	# server name.
990	# <virtualhost *:80=""></virtualhost>
991	<pre># ServerAdmin webmaster@dummy-host.example.com</pre>
992	<pre># DocumentRoot /www/docs/dummy-host.example.com</pre>
993	<pre># ServerName dummy-host.example.com</pre>
994	<pre># ErrorLog logs/dummy-host.example.com-error_log</pre>
995	<pre># CustomLog logs/dummy-host.example.com-access_log common</pre>
996	#

Annexe 3 : vsftpd.conf

#	TEXTE
1	# Example config file /etc/vsftpd/vsftpd.conf
2	#
3	# The default compiled in settings are fairly paranoid. This sample file
4	# loosens things up a bit, to make the ftp daemon more usable.
5	# Please see vsftpd.conf.5 for all compiled in defaults.
6	#
	# READ THIS: This example file is NOT an exhaustive list of vsftpd options.
7	# Please read the vsftpd.conf.5 manual page to get a full idea of vsftpd's
8	# capabilities.
10	#
12	# Allow anonymous FTP? (Beware - allowed by default if you comment this out).
13	anonymous_enable=YES
14	#
15	# Uncomment this to allow local users to log in.
16	local_enable=YES
17	#
18	# Uncomment this to enable any form of FTP write command.
19	write_enable=YES
20	#
21	<pre># Default umask for local users is 077. You may wish to change this to 022,</pre>
22	<pre># if your users expect that (022 is used by most other ftpd's)</pre>
23	local_umask=022
24	#
25	$\ensuremath{\#}$ Uncomment this to allow the anonymous FTP user to upload files. This only
26	<pre># has an effect if the above global write enable is activated. Also, you will</pre>
27	# obviously need to create a directory writable by the FTP user.

#	TEXTE
π	
28	#anon_upload_enable=YES
29	#
30	# Uncomment this if you want the anonymous FTP user to be able to create
31	<pre># new directories.</pre>
32	<pre>#anon_mkdir_write_enable=YES</pre>
33	#
34	<pre># Activate directory messages - messages given to remote users when they</pre>
35	# go into a certain directory.
36	dirmessage_enable=YES
37	#
38	<pre># The target log file can be vsftpd_log_file or xferlog_file.</pre>
39	<pre># This depends on setting xferlog_std_format parameter</pre>
40	xferlog_enable=YES
41	#
42	<pre># Make sure PORT transfer connections originate from port 20 (ftp-data).</pre>
43	<pre>connect_from_port_20=YES</pre>
44	#
45	<pre># If you want, you can arrange for uploaded anonymous files to be owned by</pre>
46	<pre># a different user. Note! Using "root" for uploaded files is not</pre>
47	<pre># recommended!</pre>
48	<pre>#chown_uploads=YES</pre>
49	<pre>#chown_username=whoever</pre>
50	#
51	<pre># The name of log file when xferlog_enable=YES and xferlog_std_format=YES</pre>
52	<pre># WARNING - changing this filename affects /etc/logrotate.d/vsftpd.log</pre>
53	<pre>#xferlog_file=/var/log/xferlog</pre>
54	#
55	<pre># Switches between logging into vsftpd_log_file and xferlog_file files.</pre>

#	TEXTE
56	<pre># NO writes to vsftpd_log_file, YES to xferlog_file</pre>
57	<pre>xferlog_std_format=YES</pre>
58	#
59	# You may change the default value for timing out an idle session.
60	<pre>#idle_session_timeout=600</pre>
61	#
62	# You may change the default value for timing out a data connection.
63	<pre>#data_connection_timeout=120</pre>
64	#
65	<pre># It is recommended that you define on your system a unique user which the</pre>
66	# ftp server can use as a totally isolated and unprivileged user.
67	<pre>#nopriv_user=ftpsecure</pre>
68	#
69	<pre># Enable this and the server will recognise asynchronous ABOR requests. Not</pre>
70	<pre># recommended for security (the code is non-trivial). Not enabling it,</pre>
71	<pre># however, may confuse older FTP clients.</pre>
72	<pre>#async_abor_enable=YES</pre>
73	#
74	<pre># By default the server will pretend to allow ASCII mode but in fact ignore</pre>
75	$\ensuremath{\texttt{\#}}$ the request. Turn on the below options to have the server actually do ASCII
76	<pre># mangling on files when in ASCII mode.</pre>
77	<pre># Beware that on some FTP servers, ASCII support allows a denial of service</pre>
78	<pre># attack (DoS) via the command "SIZE /big/file" in ASCII mode. vsftpd</pre>
79	<pre># predicted this attack and has always been safe, reporting the size of the</pre>
80	# raw file.
81	# ASCII mangling is a horrible feature of the protocol.
82	ascii_upload_enable=YES
83	ascii_download_enable=YES

#	TEXTE
84	#
85	# You may fully customise the login banner string:
86	ftpd_banner=Welcome to Lab FTP Server
87	#
88	<pre># You may specify a file of disallowed anonymous e-mail addresses. Apparently</pre>
89	<pre># useful for combatting certain DoS attacks.</pre>
90	<pre>#deny_email_enable=YES</pre>
91	# (default follows)
92	<pre>#banned_email_file=/etc/vsftpd/banned_emails</pre>
93	#
94	<pre># You may specify an explicit list of local users to chroot() to their home</pre>
95	<pre># directory. If chroot_local_user is YES, then this list becomes a list of</pre>
96	<pre># users to NOT chroot().</pre>
97	chroot_local_user=YES
98	<pre>#chroot_list_enable=YES</pre>
99	# (default follows)
100	chroot_list_file=/etc/vsftpd/chroot_list
101	#
102	# You may activate the "-R" option to the builtin ls. This is disabled by
103	<pre># default to avoid remote users being able to cause excessive I/O on large</pre>
104	<pre># sites. However, some broken FTP clients such as "ncftp" and "mirror" assume</pre>
105	# the presence of the "-R" option, so there is a strong case for enabling it.
106	<pre>#ls_recurse_enable=YES</pre>
107	#
108	# When "listen" directive is enabled, vsftpd runs in standalone mode and
109	<pre># listens on IPv4 sockets. This directive cannot be used in conjunction</pre>
110	<pre># with the listen_ipv6 directive.</pre>
111	listen=YES

#	TEXTE
112	#
113	# This directive enables listening on IPv6 sockets. To listen on IPv4 and IPv6
114	<pre># sockets, you must run two copies of vsftpd with two configuration files.</pre>
115	<pre># Make sure, that one of the listen options is commented !!</pre>
116	<pre>#listen_ipv6=YES</pre>
117	
118	<pre>pam_service_name=vsftpd</pre>
119	userlist_enable=YES
120	tcp_wrappers=YES

Votes	

